

SYBASE®

Connection Reference

**PowerBuilder®**

10.5

DOCUMENT ID: DC33820-01-1050-01

LAST REVISED: March 2006

Copyright © 1991-2006 by Sybase, Inc. All rights reserved.

This publication pertains to Sybase software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

To order additional documents, U.S. and Canadian customers should call Customer Fulfillment at (800) 685-8225, fax (617) 229-9845.

Customers in other countries with a U.S. license agreement may contact Customer Fulfillment via the above fax number. All other international customers should contact their Sybase subsidiary or local distributor. Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc.

Sybase, the Sybase logo, ADA Workbench, Adaptable Windowing Environment, Adaptive Component Architecture, Adaptive Server, Adaptive Server Anywhere, Adaptive Server Enterprise, Adaptive Server Enterprise Monitor, Adaptive Server Enterprise Replication, Adaptive Server Everywhere, Adaptive Warehouse, Afaia, Answers Anywhere, Anywhere Studio, Application Manager, AppModeler, APT Workbench, APT-Build, APT-Edit, APT-Execute, APT-Translator, APT-Library, AvantGo Mobile Delivery, AvantGo Mobile Inspection, AvantGo Mobile Marketing Channel, AvantGo Mobile Pharma, AvantGo Mobile Sales, AvantGo Pylon, AvantGo Pylon Application Server, AvantGo Pylon Conduit, AvantGo Pylon PIM Server, AvantGo Pylon Pro, Backup Server, BizTracker, ClearConnect, Client-Library, Client Services, Convoy/DM, Copernicus, Data Pipeline, Data Workbench, DataArchitect, Database Analyzer, DataExpress, DataServer, DataWindow, DataWindow .NET, DB-Library, dbQueue, Developers Workbench, DirectConnect, DirectConnect Anywhere, Distribution Director, e-ADK, E-Anywhere, e-Biz Impact, e-Biz Integrator, E-Whatever, EC Gateway, ECMAP, ECRTIP, eFulfillment Accelerator, Embedded SQL, EMS, Enterprise Application Studio, Enterprise Client/Server, Enterprise Connect, Enterprise Data Studio, Enterprise Manager, Enterprise SQL Server Manager, Enterprise Work Architecture, Enterprise Work Designer, Enterprise Work Modeler, eProcurement Accelerator, EWA, Financial Fusion, Financial Fusion Server, Gateway Manager, GlobalFIX, iAnywhere, iAnywhere Solutions, ImpactNow, Industry Warehouse Studio, InfoMaker, Information Anywhere, Information Everywhere, InformationConnect, InternetBuilder, iScript, Jaguar CTS, jConnect for JDBC, M2M Anywhere, Mach Desktop, Mail Anywhere Studio, Mainframe Connect, Maintenance Express, Manage Anywhere Studio, M-Business Anywhere, M-Business Channel, M-Business Network, M-Business Suite, MDI Access Server, MDI Database Gateway, media.splash, MetaWorks, mFolio, Mirror Activator, MySupport, Net-Gateway, Net-Library, New Era of Networks, ObjectConnect, ObjectCycle, OmniConnect, OmniSQL Access Module, OmniSQL Toolkit, Open Biz, Open Client, Open ClientConnect, Open Client/Server, Open Client/Server Interfaces, Open Gateway, Open Server, Open ServerConnect, Open Solutions, Optima++, PB-Gen, PC APT Execute, PC DB-Net, PC Net Library, Pharma Anywhere, PocketBuilder, Pocket PowerBuilder, Power++, power.stop, PowerAMC, PowerBuilder, PowerBuilder Foundation Class Library, PowerDesigner, PowerDimensions, PowerDynamo, PowerScript, PowerSite, PowerSocket, Powersoft, PowerStage, PowerStudio, PowerTips, Powersoft Portfolio, Powersoft Professional, PowerWare Desktop, PowerWare Enterprise, ProcessAnalyst, QAnywhere, Rapport, RemoteWare, RepConnector, Replication Agent, Replication Manager, Replication Server, Replication Server Manager, Replication Toolkit, Report-Execute, Report Workbench, Resource Manager, RFID Anywhere, RW-DisplayLib, RW-Library, Sales Anywhere, SDF, Search Anywhere, Secure SQL Server, Secure SQL Toolset, Security Guardian, SKILLS, smart.partners, smart.parts, smart.script, SOA Anywhere, SQL Advantage, SQL Anywhere, SQL Anywhere Studio, SQL Code Checker, SQL Debug, SQL Edit, SQL Edit/TPU, SQL Everywhere, SQL Modeler, SQL Remote, SQL Server, SQL Server Manager, SQL SMART, SQL Toolset, SQL Server/CFT, SQL Server/DBM, SQL Server SNMP SubAgent, SQL Station, SQLJ, STEP, SupportNow, S.W.I.F.T. Message Format Libraries, Sybase Central, Sybase Client/Server Interfaces, Sybase Financial Server, Sybase Gateways, Sybase IQ, Sybase MPP, Sybase SQL Desktop, Sybase SQL Lifecycle, Sybase SQL Workgroup, Sybase User Workbench, SybaseWare, Syber Financial, SyberAssist, SybFlex, SyBooks, System 10, System 11, System XI (logo), SystemTools, Tabular Data Stream, TradeForce, Transact-SQL, Translation Toolkit, UltraLite, UltraLite.NET, UNIBOM, Unilib, Uninull, Unisep, Unistring, URK Runtime Kit for UniCode, VisualWriter, VQL, WarehouseArchitect, Warehouse Control Center, Warehouse Studio, Warehouse WORKS, Watcom, Watcom SQL, Watcom SQL Server, Web Deployment Kit, Web.PB, Web.SQL, WebSights, WebViewer, WorkGroup SQL Server, XA-Library, XA-Server, XcelleNet, and XP Server are trademarks of Sybase, Inc. 10/05

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

All other company and product names used herein may be trademarks or registered trademarks of their respective companies.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS 52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Sybase, Inc., One Sybase Drive, Dublin, CA 94568.

# Contents

<b>About This Book</b> .....	<b>vii</b>
<b>CHAPTER 1</b>	<b>Database Parameters</b> ..... <b>1</b>
	Database parameters and supported database interfaces ..... 1
	ADORelease ..... 6
	AppName ..... 7
	Async..... 8
	BindSPInput ..... 10
	BinTxtBlob ..... 11
	Block (ODBC, OLE DB, and Oracle) ..... 13
	Block (DirectConnect and Adaptive Server Enterprise) ..... 15
	CacheAuthentication ..... 16
	CacheName ..... 16
	CallEscape ..... 18
	CharSet ..... 19
	CnnPool..... 20
	CommandTimeout..... 21
	CommitOnDisconnect ..... 22
	ConnectAs..... 23
	ConnectOption ..... 24
	ConnectString..... 28
	CursorLib..... 30
	CursorLock ..... 30
	CursorScroll..... 31
	CursorType..... 33
	CursorUpdate ..... 34
	Database ..... 35
	DataLink ..... 36
	DataSource ..... 37
	Date ..... 38
	DateFormat ..... 41
	DateTime ..... 42
	DateTimeAllowed ..... 44
	DateTimeFormat ..... 46

DBConfigSection .....	47
DBGetTime .....	49
DBTextLimit .....	50
DecimalSeparator .....	51
DefaultProcOwner .....	53
DelimitIdentifier .....	54
DisableBind .....	56
DisableUnicode .....	59
Driver .....	60
DS_Alias .....	61
DS_Copy .....	63
DS_DitBase .....	65
DS_Failover .....	68
DS_Password .....	70
DS_Principal .....	72
DS_Provider .....	73
DS_TimeLimit .....	75
EncryptPassword .....	77
FoDelay .....	78
FoDialog .....	78
FoRetryCount .....	79
FormatArgsAsExp .....	80
GetConnectionOption .....	82
Host .....	83
HostReqOwner .....	85
IdentifierQuoteChar .....	86
ImpersonationLevel .....	88
INET_DBPATH .....	89
INET_PROTOCOL .....	90
INET_SERVICE .....	91
Init_Prompt .....	92
InsertBlock .....	92
IntegratedSecurity .....	94
Isolation .....	95
JavaVM .....	96
KeepAlive .....	97
Language .....	98
LCID .....	99
Locale .....	100
Location .....	102
Log .....	102
LoginTimeOut .....	103
LowerCasIdent .....	103
MaskPassword .....	104

MaxConnect .....	105
MaxFetchBuffer .....	106
MixedCase .....	107
Mode .....	108
MsgTerse .....	109
Namespace .....	110
NCharBind .....	111
NumbersInternal .....	112
NumericFormat .....	113
ObjectMode .....	115
ODBCU_CONLIB .....	116
OJSyntax .....	117
OraMTSConFlgs .....	119
PackageProcs .....	120
PacketSize (ODBC) .....	121
PacketSize (DIR, SYC) .....	122
PBCatalogOwner .....	123
PBMaxBlobSize .....	126
PBNewSPInvocation .....	127
PBTrimCharColumns .....	128
PBUseProcOwner .....	129
PersistEncrypted .....	131
PersistSensitive .....	132
Properties .....	133
ProtectionLevel .....	134
Provider .....	135
ProviderString .....	136
ProxyUserName .....	137
PWDialog .....	138
PWEncrypt .....	139
PWExpDialog .....	140
QualifyPublic .....	141
Release .....	142
ReleaseConnectionOption .....	144
Request .....	146
RPCRebind .....	147
ReturnCommandHandle .....	148
Scroll .....	148
Sec_Channel_Bind .....	149
Sec_Confidential .....	151
Sec_Cred_Timeout .....	152
Sec_Data_Integrity .....	154
Sec_Data_Origin .....	156
Sec_Delegation .....	157

- Sec\_Keytab\_File ..... 159
- Sec\_Mechanism..... 161
- Sec\_Mutual\_Auth ..... 163
- Sec\_Network\_Auth..... 165
- Sec\_Replay\_Detection..... 167
- Sec\_Seq\_Detection..... 169
- Sec\_Server\_Principal..... 170
- Sec\_Sess\_Timeout ..... 172
- ServiceComponents ..... 174
- ShowWarnings ..... 174
- SPCache ..... 175
- SQLCache..... 176
- SQLQualifiers ..... 178
- StaticBind ..... 179
- StripParmNames ..... 181
- SvrFailover ..... 182
- SystemOwner..... 183
- SystemProcs ..... 184
- TableCriteria..... 185
- ThreadSafe..... 187
- Time ..... 188
- TimeFormat ..... 191
- Timeout ..... 192
- TimeStamp ..... 192
- TraceFile ..... 194
- TrimSpaces ..... 195
- TrustedConnection ..... 196
- TRS ..... 197
- URL ..... 197
- UseContextObject ..... 199
- UseProcSyntax..... 201
- UTF8 ..... 201

**CHAPTER 2 Database Preferences ..... 203**

- Database preferences and supported database interfaces ..... 203
- AutoCommit..... 205
- Connect to Default Profile ..... 208
- Keep Connection Open ..... 209
- Lock..... 210
- Read Only ..... 214
- Shared Database Profiles ..... 215
- SQL Terminator Character ..... 216
- Use Extended Attributes..... 217

**Index ..... 219**

# About This Book

<b>Audience</b>	This book is for anyone who uses PowerBuilder® to connect to a database. It assumes that you are familiar with the database you are using and have installed the server and client software required to access the data.
<b>How to use this book</b>	This book describes the database parameters and preferences you use to connect to a database in PowerBuilder.
<b>Related documents</b>	<p>For information about connecting to a database in the PowerBuilder development environment, see <i>Connecting to Your Database</i>.</p> <p>For a complete list of PowerBuilder documentation, see the preface of <i>Getting Started</i>.</p>
<b>Other sources of information</b>	<p>Use the Sybase Getting Started CD, the SyBooks CD, and the Sybase Product Manuals Web site to learn more about your product:</p> <ul style="list-style-type: none"><li>• The Getting Started CD contains release bulletins and installation guides in PDF format, and may also contain other documents or updated information not included on the SyBooks CD. It is included with your software. To read or print documents on the Getting Started CD, you need Adobe Acrobat Reader, which you can download at no charge from the Adobe Web site using a link provided on the CD.</li><li>• The SyBooks CD contains product manuals and is included with your software. The Eclipse-based SyBooks browser allows you to access the manuals in an easy-to-use, HTML-based format.</li></ul> <p>Some documentation may be provided in PDF format, which you can access through the PDF directory on the SyBooks CD. To read or print the PDF files, you need Adobe Acrobat Reader.</p> <p>Refer to the <i>SyBooks Installation Guide</i> on the Getting Started CD, or the <i>README.txt</i> file on the SyBooks CD for instructions on installing and starting SyBooks.</p>

- 
- The Sybase Product Manuals Web site is an online version of the SyBooks CD that you can access using a standard Web browser. In addition to product manuals, you will find links to EBFs/Maintenance, Technical Documents, Case Management, Solved Cases, newsgroups, and the Sybase Developer Network.

To access the Sybase Product Manuals Web site, go to Product Manuals at <http://www.sybase.com/support/manuals/>.

**If you need help**

Each Sybase installation that has purchased a support contract has one or more designated people who are authorized to contact Sybase Technical Support. If you cannot resolve a problem using the manuals or online help, please have the designated person contact Sybase Technical Support or the Sybase subsidiary in your area.



About this chapter

This chapter describes the syntax and use of each database parameter that you can set in PowerBuilder.

---

**Setting database parameters in code**

Use the Preview page of the Database Connection Profile dialog box to ensure that you are using the correct syntax in code. Most boolean database parameters can be turned on using any of the values TRUE, Yes, or 1, and turned off using FALSE, No, or 0. Numeric values for database parameters must not be enclosed in quotes.

---

## Database parameters and supported database interfaces

The following table lists each supported database interface and the database parameters you can use with that interface in PowerBuilder.

The database parameters are described in alphabetical order following the table.

Database interface	DBParm parameters	
ADO.NET	ADORelease CommandTimeout CommitOnDisconnect Database DataLink DataSource DateFormat DateTimeFormat DBConfigSection DecimalSeparator DefaultProcOwner DelimitIdentifier DisableBind IdentifierQuoteChar	Isolation Namespace NCharBind (Oracle only) OJSyntax PBCatalogOwner PBMaxBlobSize Provider ProviderString SPCache StaticBind TimeFormat Timeout TrimSpaces TrustedConnection
DIR Sybase DirectConnect™	AppName Async Block (DirectConnect and Adaptive Server Enterprise) CharSet CommitOnDisconnect CursorUpdate DateTimeAllowed DBGetTime DBTextLimit DecimalSeparator DelimitIdentifier FormatArgsAsExp HostReqOwner Language	Locale LowerCaseIdent MaxConnect PacketSize (DIR, SYC) PBCatalogOwner Request ShowWarnings SQLQualifiers StaticBind SystemOwner TableCriteria TrimSpaces TRS UseProcSyntax UTF8
IN9 Informix	Async CommitOnDisconnect DateTimeAllowed DBGetTime DecimalSeparator DelimitIdentifier DisableBind	INET_DBPATH INET_PROTOCOL INET_SERVICE OJSyntax Scroll ThreadSafe

Database interface	DBParm parameters	
JDBC	Async CacheName CommitOnDisconnect Date DateTime DBGetTime DelimitIdentifier DisableBind Driver FormatArgsAsExp GetConnectionOption IdentifierQuoteChar JavaVM (JDB only) LoginTimeout	MsgTerse NumericFormat OJSyntax PBCatalogOwner Properties ProxyUserName ReleaseConnectionOption StaticBind TableCriteria Time TraceFile TrimSpaces URL UseContextObject
ODBC	Async Block (ODBC, OLE DB, and Oracle) CacheName CallEscape CommitOnDisconnect ConnectOption ConnectString CursorLib CursorLock CursorScroll Date DateTime DBGetTime DecimalSeparator DefaultProcOwner DelimitIdentifier DisableBind FormatArgsAsExp GetConnectionOption IdentifierQuoteChar InsertBlock	LoginTimeout MsgTerse NumericFormat ODBCUCONLIB OJSyntax PacketSize (ODBC) PBCatalogOwner PBNewSPInvocation PBTrimCharColumns PBUseProcOwner ProxyUserName ReleaseConnectionOption RPCRebind SQLCache StaticBind StripParmNames TableCriteria Time TrimSpaces UseContextObject
<hr/> <b>Using DBParms with ODBC</b> These database parameters are supported by the PowerBuilder ODBC interface only if <i>both</i> the ODBC driver you are using and the back-end DBMS support the feature <hr/>		

Database interface	DBParm parameters	
OLE DB	BinTxtBlob Block (ODBC, OLE DB, and Oracle) CacheAuthentication CommitOnDisconnect DataLink DataSource DateFormat DateTimeFormat DecimalSeparator DelimitIdentifier DisableBind EncryptPassword IdentifierQuoteChar ImpersonationLevel Init_Prompt IntegratedSecurity LCID	Location MaskPassword Mode OJSyntax PBCatalogOwner PBMaxBlobSize PBTrimCharColumns PersistEncrypted PersistSensitive ProtectionLevel Provider ProviderString ReturnCommandHandle ServiceComponents StaticBind TimeFormat Timeout
O84 Oracle 8.x and Oracle8i O90 Oracle9i O10 Oracle 10g	Async BindSPInput BinTxtBlob Block (ODBC, OLE DB, and Oracle) CacheName CnnPool (O90 and later) CommitOnDisconnect ConnectAs (O90 and later) Date DateTime DBGetTime DecimalSeparator DelimitIdentifier DisableBind DisableUnicode (O84 only) FoDelay FoDialog FoRetryCount FormatArgsAsExp GetConnectionOption MaxFetchBuffer	MixedCase NCharBind (O90 and later) NumbersInternal ObjectMode OJSyntax OraMTSConFlgs PackageProcs PBCatalogOwner PWDialog PWExpDialog QualifyPublic ReleaseConnectionOption SQLCache StaticBind SvrFailover TableCriteria ThreadSafe Time TimeStamp (O90 and later) UseContextObject

Database interface	DBParm parameters	
SYC Sybase Adaptive Server® Enterprise  <hr/> <b>Set Release</b> The Release database parameter must be set to the version of your Open Client® software (11 or higher) to use DS_* and Sec_* parameters.	AppName Async BinTxtBlob Block (DirectConnect and Adaptive Server Enterprise) CharSet CommitOnDisconnect CursorType CursorUpdate DateTimeAllowed DBGetTime DBTextLimit DelimitIdentifier DS_Alias DS_Copy DS_DitBase DS_Failover DS_Password DS_Principal DS_Provider DS_TimeLimit FoDialog FormatArgsAsExp Host KeepAlive Language Locale Log MaxConnect	OJSyntax PacketSize (DIR, SYC) PBCatalogOwner ProxyUserName PWDialog PWEcrypt PWExpDialog Release Sec_Channel_Bind Sec_Confidential Sec_Cred_Timeout Sec_Data_Integrity Sec_Data_Origin Sec_Delegation Sec_Keytab_File Sec_Mechanism Sec_Mutual_Auth Sec_Network_Auth Sec_Replay_Detection Sec_Seq_Detection Sec_Server_Principal Sec_Sess_Timeout StaticBind SvrFailover SystemProcs TableCriteria TrimSpaces UTF8
SYJ Sybase Adaptive Server Enterprise	Block (DirectConnect and Adaptive Server Enterprise) CacheName CursorUpdate DBTextLimit FormatArgsAsExp GetConnectionOption Log PBCatalogOwner	ProxyUserName ReleaseConnectionOption StaticBind SvrFailover SystemProcs TrimSpaces UseContextObject UTF8

## ADORelease

**Description** Specifies the version of the ADO.NET data provider that is in use on the client workstation.

---

**When to specify ADORelease**

You must specify a value for ADORelease *before* connecting to the database.

---

**Applies to** ADO.NET

**Syntax** **ADORelease** = '*value*'

Parameter	Description
<i>value</i>	<p>Specifies the version of an ADO.NET data provider your application uses.</p> <p>For Sybase Adaptive Server Enterprise, the optional values are:</p> <ul style="list-style-type: none"> <li>• <b>1.1.411.0</b> For Adaptive Server 12.5.x clients</li> <li>• <b>1.15.50.0</b> For Adaptive Server 15.x clients</li> </ul> <p>For Oracle, the optional values are:</p> <ul style="list-style-type: none"> <li>• <b>9.2.0.401</b> For Oracle9i clients</li> <li>• <b>10.1.0.301</b> For Oracle 10g clients</li> </ul>

**Default value** 1.1.411.0 for Adaptive Server, 9.2.0.401 for Oracle.

**Usage** The ADORelease database parameter specifies the version of the ADO.NET database provider used for native connections to a database server using ADO.NET.

For Adaptive Server, specify Sybase.Data.AseClient as the Namespace in the Database Profile Setup dialog box for ADO.NET to display available versions of the Sybase ASE ADO.NET Data Provider in the Release drop-down list.

The database provider is supplied in the .NET assemblies *Sybase.PowerBuilder.Db.dll* (for Adaptive Server 12.5.x and Oracle9i) and *Sybase.PowerBuilder.DbExt.dll* (for Adaptive Server 15.x and Oracle 10g). You must deploy the appropriate version of this DLL with your application.

For Oracle, specify Oracle.DataAccessClient as the Namespace in the Database Profile Setup dialog box for ADO.NET to display available versions of the Oracle Data provider for .NET (ODP.NET) in the Release drop-down list.

When you select a driver version, the ADO.NET interface attempts to load that driver. If the driver is redirected to a higher version of the driver, the higher driver is loaded, but only the features in the selected driver may be supported. For example with Oracle ODP.NET, if ADORelease is set to 9.2.0.401 but the policy file on your computer redirects the driver to version 10.1.0.301, the ODP.NET 10.1.0.301 driver is loaded. New features in ODP.NET 10.1.0.301 are not supported.

#### Examples

To specify that your PowerBuilder application accesses an Adaptive Server Enterprise 15 database using the ASE ADO.NET Data Provider:

- **Database profile** Select 1.1.50.0 from the ADORelease drop-down list on the Connection tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="ADORelease='1.15.50.0'"
```

## AppName

#### Description

If the DBMS supports it, specifies the application name you want to use when connecting to the database in PowerBuilder.

---

#### When to specify AppName

You must specify the AppName parameter *before* connecting to the database.

---

#### Applies to

DIR Sybase DirectConnect  
SYC Sybase Adaptive Server Enterprise

#### Syntax

**AppName** = '*application\_name*'

#### Default value

PowerBuilder sets the CS\_APPNAME connection property to PowerBuilder, as follows:

```
AppName = 'PowerBuilder'
```

#### Usage

*Adaptive Server databases* It is useful to specify a different AppName value for each of your Adaptive Server applications. If you are an administrator, you can query the MASTER.DBO.SYSPROCESSES table to determine which applications are running on the database server. The value specified for AppName displays in the program\_name column of the MASTER.DBO.SYSPROCESSES table, making it easy to identify the applications.

Examples

**Example 1** To set the application name to Test:

- **Database profile** Type the following in the Application Name box on the Network tab in the Database Profile Setup dialog box:

```
Test
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "AppName='Test' "
```

**Example 2** (*Does not apply to DirectConnect*) You can set the AppName and Host parameters in a single statement to specify both the application name and the host name. To set the application name to Sales and the host name to Fran:

- **Database profile** Type Sales in the Application Name box and Fran in the Workstation Name box on the Network tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "AppName='Sales',Host='Fran' "
```

See also

Host (applies only to SYC Sybase Adaptive Server Enterprise)

## Async

Description

Allows you to perform asynchronous operations on your database in PowerBuilder. If you have coded a RetrieveRow event for a DataWindow object or report, you can cancel the current database retrieval operation or start another (non-database) operation that does not use the same database connection before the current operation completes. You can also switch to another Windows process while the retrieval takes place.

By default, PowerBuilder operates synchronously.

Applies to

DIR Sybase DirectConnect  
 IN9 Informix  
 JDB JDBC  
 ODBC (if driver and back-end DBMS support this feature)  
 O84 Oracle 8.x and Oracle8i (8.1.5 and higher database connections only)  
 O90 Oracle9i  
 O10 Oracle 10g  
 SYC Sybase Adaptive Server Enterprise



## Syntax

**Async = value**

Parameter	Description
<i>value</i>	A value specifying synchronous or asynchronous operation. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Synchronous operation</li> <li>• <b>1</b> Asynchronous operation</li> </ul>

## Default value

Async = 0

## Usage

Enabling asynchronous operation in PowerBuilder is useful when you are executing a complex SQL statement that takes several minutes to return results. If the Async parameter is set to 1, you can do either of the following while the SQL statement is executing:

- Work in another window
- Cancel the statement before it retrieves the first row of data

*When to set Async* If you are communicating with the database in code, you can reset the Async value at any time before or after the Transaction object has connected to the database.

*How data is retrieved* When you retrieve data in a DataWindow object or report, the following steps occur in order:

- 1 The database server compiles and executes the SQL statement.
- 2 PowerBuilder retrieves (fetches) the first row of data.
- 3 PowerBuilder retrieves each subsequent row of data.

*What happens before the first row is retrieved* While the server is compiling and executing the SQL statement and before PowerBuilder retrieves the first row of data, you must have done *both* of the following to enable asynchronous operation (allowing you to cancel the current operation before it retrieves the first row of data):

- Coded a RetrieveRow event for the DataWindow object or report (the code can contain only a comment)
- Set the Async parameter to 1

*What happens after the first row is retrieved* After the first row of data is retrieved and between subsequent row fetches, you must have done only the following to enable asynchronous operation:

- Coded a RetrieveRow event for the DataWindow object or report

After the first row is retrieved, PowerBuilder operates asynchronously *without your having to set the Async parameter to 1*, so you can cancel the current operation anytime after it retrieves the first row of data. Therefore, the Async parameter has no effect in PowerBuilder after the first row of data is retrieved.

Examples

**Example 1** To enable asynchronous operation:

- **Database profile** Select the Asynchronous check box on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Async=1"
```

**Example 2** You can set the Async and DBGetTime parameters in a single statement. DBGetTime specifies the number of seconds you want PowerBuilder to wait for a response from the DBMS when you retrieve rows in a DataWindow object or report. To enable asynchronous operation and set the DBGetTime parameter to 20 seconds:

- **Database profile** Select the Asynchronous check box and type 20 in the Number Of Seconds To Wait box on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Async=1,DBGetTime=20"
```

See also

DBGetTime

## BindSPInput

Description

Specifies that PowerBuilder bind input parameters in dynamic SQL statements when executing a stored procedure.

Applies to

O84 Oracle 8.x and Oracle8i  
O90 Oracle9i

Syntax

**BindSPInput** = *value*

Parameter	Description
<i>value</i>	<p>Specifies whether you want to bind input parameters in dynamic SQL statements when executing stored procedures. Values are:</p> <ul style="list-style-type: none"> <li>• <b>No</b> (Default) PowerBuilder does not bind parameters in dynamic SQL statements when executing stored procedures.</li> <li>• <b>Yes</b> PowerBuilder binds parameters in dynamic SQL statements when executing stored procedures.</li> </ul>

Default value	BindSPInput = 'No'
Examples	To specify that PowerBuilder should bind parameters in dynamic SQL statements when executing a stored procedure, type the following in a script: <pre>SQLCA.DBParm = "BindSPInput = 'Yes'"</pre>
See also	DisableBind

## BinTxtBlob

Description	Specifies that binary data or an ANSI string is to be submitted to or retrieved from a text column with UPDATEBLOB or SELECTBLOB.
Applies to	OLE DB O84 Oracle 8.x and Oracle8i O90 Oracle9i O10 Oracle 10g SYC Sybase Adaptive Server Enterprise
Syntax	<b>BinTxtBlob</b> = <i>value</i>

Parameter	Description
<i>value</i>	Specifies that a PowerBuilder blob that is submitted to a text column in a database with UPDATEBLOB or retrieved with SELECTBLOB contains binary data or an ANSI string. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> The blob contains a Unicode string.</li> <li>• <b>1</b> The blob contains any kind of data that is not regarded as a Unicode string.</li> </ul>

Default value	BinTxtBlob=0
Usage	By default, when you use the UPDATEBLOB and SELECTBLOB SQL statements with a database column with a text datatype (long or clob for Oracle or text for Adaptive Server or OLE DB access to SQL Server), the PowerBuilder blob that is updated or selected is expected to contain a Unicode string. If the blob contains any other kind of data, such as binary data or an ANSI string, set the BinTxtBlob database parameter to 1 before calling SELECTBLOB or UPDATEBLOB. This prevents PowerBuilder or the database server from attempting to perform any conversion to or from Unicode.

*Oracle O84* The Oracle O84 interface uses an ANSI database handle. With the default setting (BinTxtBlob=0) and UPDATEBLOB, the O84 interface converts the Unicode string to ANSI or UTF-8 based on the client's NLS\_LANG setting before sending the data to the server. For SELECTBLOB, the O84 interface gets an ANSI or UTF-8 string from the server and converts it to a Unicode (UCS-2) string.

With BinTxtBlob set to 1, the O84 interface transfers the data directly with no conversion.

*Oracle O90 and O10* The Oracle O90 and O10 interfaces use a Unicode database handle. With the default setting (BinTxtBlob=0) and UPDATEBLOB, they send the data directly to the Oracle server and inform the server that the binary data contains Unicode strings. Any conversion needed is performed by the server. For SELECTBLOB, they get a Unicode string from the server.

When BinTxtBlob is set to 1, the value of the NLS\_LANG environment variable determines the binding character set. The ANSI string or binary data is transferred directly to or from the server as in PowerBuilder 9 and previous releases.

To set BinTxtBlob to 1 with the O90 interface, you must use an Oracle 9.2 or later client, or you will receive an error.

*OLE DB and SYC* If BinTxtBlob is set to 0, the OLE DB and SYC interfaces perform any necessary conversion. If BinTxtBlob is set to 1, the data is passed to the server without conversion.

## Examples

In code, before calling SELECTBLOB or UPDATEBLOB with a PowerBuilder blob that contains ANSI string data or binary data, set the BinTxtBlob parameter to 1:

```
SQLCA.DBParm = "BinTxtBlob=1"
```

Restore the default setting of 0 if an operation needs to be performed on a blob that contains Unicode string data.

For example, suppose a Unicode string "ABC" stored in client memory as "65 00 66 00 67 00" is updated to the database using UPDATEBLOB. If BinTxtBlob is set to 0, the data is converted to ANSI and stored in the database text column as "65 66 67". If BinTxtBlob is set to 1, no conversion occurs and the data is stored in its original form as "65 00 66 00 67 00".

## Block (ODBC, OLE DB, and Oracle)

**Description** For those interfaces that support it, Block specifies the cursor blocking factor when connecting to a database. The blocking factor determines the number of rows that a DataWindow object can fetch from the database at one time.

Using the Block parameter can improve performance when accessing a database in PowerBuilder.

**Applies to** ODBC (if driver and back-end DBMS support this feature)  
OLE DB  
O84 Oracle 8.x and Oracle8i  
O90 Oracle9i  
O10 Oracle 10g

**Syntax** **Block** = *blocking\_factor*

Parameter	Description
<i>blocking_factor</i>	The number of rows you want the DataWindow object to fetch from the database at one time. The blocking factor can be a number from 1 to 1000, inclusive.  To turn off block fetching, set Block to 1.

**Default value** The default value for the Block parameter depends on the DBMS you are accessing, as summarized in the following table:

DBMS	Block default value
ODBC	For most DataWindow objects, the Block default value is the following, <i>up to a maximum of 32K per column</i> :  Block = 1000  If you specified that the DataWindow object should retrieve only as many rows as needed from the database (Retrieve.AsNeeded property), the Block default value is the following, <i>up to a maximum of 32K per column</i> :  Block = 100
OLE DB	PowerBuilder sets the blocking factor to 1
Oracle	PowerBuilder sets the blocking factor to 300 rows.

### Using the default blocking factor

You should not have to set a non-default value for Block. In most cases, the default blocking factor used by PowerBuilder should meet your needs.

Usage

*Requirements for ODBC data sources* To use the Block DBParm parameter with an ODBC data source, your ODBC driver must:

- Be ODBC Version 2.0 compliant or higher, *and*
- Support the SQLExtendedFetch API call

The Adaptive Server® Anywhere ODBC driver that comes with PowerBuilder meets both of these requirements.

For information about whether your ODBC driver meets these requirements, see the documentation that comes with your driver.

*Determining the Block value for ODBC data sources* PowerBuilder searches the following in this order to determine the Block value for ODBC data sources:

- 1 The section for your database profile in the registry or the value of the Transaction object property (in an application)
- 2 The section for your ODBC driver in the PBODB105 initialization file

If PowerBuilder does not find a Block value in these locations, it uses the default Block value for the DBMS you are accessing.

*Turning off block fetching* To turn off block fetching for an ODBC data source or Oracle database, set the Block parameter to 1.

For Oracle, the Block parameter can be used in conjunction with the MaxFetchBuffer database parameter to improve performance when the size of a row is very large. The MaxFetchBuffer parameter has a default value of 5000000 bytes, which is sufficient for most applications. The size of the actual fetch buffer is the product of the value of the blocking factor and the size of the row.

If the fetch buffer required by the blocking factor and the row size is greater than the value of MaxFetchBuffer, the value of the blocking factor is adjusted so that the buffer is not exceeded. For example, if block = 500 and the row size is 10KB, the fetch buffer is 5000KB, which equals the default maximum buffer size.

Examples

To set the blocking factor for DataWindow objects to 50 rows:

- **Database profile** Type 50 in the Retrieve Blocking Factor box on the Transaction tab in the Database Profile Setup dialog box:
- **Application** Type the following in code:  
`SQLCA.DBParm = "Block=50"`

See also

MaxFetchBuffer

## Block (DirectConnect and Adaptive Server Enterprise)

**Description** Specifies the internal blocking factor used by the Sybase Client Library (CT-Lib) interface when declaring a cursor. The blocking factor determines the number of rows fetched from the database at one time when CT-Lib makes a physical request for data.

The Block DBParm parameter applies only to declared cursors and *not* to DataWindow objects.

**Applies to** DIR Sybase DirectConnect  
SYC and SYJ Sybase Adaptive Server Enterprise

**Syntax** **Block** = *blocking\_factor*

Parameter	Description
<i>blocking_factor</i>	The number of rows fetched from the database at one time when CT-Lib makes a physical request for data (default = 100 rows)

**Default value** Block = 100

**Examples** **Example 1** To set the blocking factor to 1000 rows:

- **Database profile** Type the following in the Retrieve Blocking Factor box on the Transaction tab in the Database Profile Setup dialog box:

```
1000
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "Block=1000"
```

**Example 2** The following embedded SQL statements show how to set the blocking factor in code and use it to declare a cursor. These statements set the blocking factor to 1000 rows and declare a cursor that uses this internal blocking factor.

```
SQLCA.DBParm = "Block=1000"
DECLARE dept_cursor CURSOR FOR
    SELECT dept_id, dept_name FROM department
    USING SQLCA;
OPEN dept_cursor;
```

## CacheAuthentication

**Description** Specifies whether the OLE DB data provider can cache sensitive authentication information, such as a password, in an internal cache.

---

### When to specify CacheAuthentication

You must specify the CacheAuthentication parameter *before* connecting to the database.

---

**Applies to** OLE DB

**Syntax** `CacheAuthentication = 'value'`

Parameter	Description
<i>value</i>	Specifies whether the OLE DB data provider can cache authentication information. Values are: <ul style="list-style-type: none"><li>• <b>True</b> Tells the OLE DB data provider to cache information.</li><li>• <b>False</b> (Default) Tells the OLE DB data provider not to cache information.</li></ul>

**Default value** CacheAuthentication = 'False'

**Examples** To tell the OLE DB data provider to cache authentication information:

- **Database profile** Select the Cache Authentication check box on the Security tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "CacheAuthentication='True'"
```

**See also** DataLink  
IntegratedSecurity

## CacheName

**Description** Allows PowerBuilder to specify an EA Server connection cache by name. This database parameter applies *only* when a PowerBuilder custom class user object is deployed as an EA Server component.

**Applies to** JDB JDBC  
ODBC  
O84 Oracle 8.x and Oracle8i  
O90 Oracle9i  
SYJ Sybase Adaptive Server Enterprise



**Using the SYJ interface**

Sybase EAServer uses a slightly different version of the CT-Lib software. Therefore, *at runtime*, you need to use the SYJ database interface rather than SYC to connect to an Adaptive Server Enterprise database. The SYJ Database Profile Setup dialog box provides a convenient way to set the appropriate connection parameters and then copy the syntax from the Preview tab into the script for your Transaction object.

You cannot use the SYJ interface, however, to connect to the database in the PowerBuilder development environment. Therefore, *during the development phase* (before the component has been deployed to EAServer), you must use SYC to connect to the database.

Syntax	<b>CacheName = 'value'</b>
Default value	None
Usage	<p>When you create a PowerBuilder custom class user object that uses an EAServer connection cache, you must specify a user name, password, server name, and connectivity library. However, if the “enable cache-by-name access” option has been enabled on EAServer, you just need to enter the connection cache name to specify the connection cache.</p> <p>For information on how to use PowerBuilder to build EAServer components, see <i>Application Techniques</i>.</p> <p>This parameter cannot be set dynamically. The value set when the connection is made remains in effect until it is disconnected.</p>
Examples	<p>On the EAServer tab in the Database Profile Setup dialog box, select the Access Cache By Name check box and enter the EAServer cache name in the Cache Name box. The PowerScript syntax for the CacheName DBParm parameter displays on the Preview tab:</p> <pre>SQLCA.DBParm = "CacheName = 'mydbcache' "</pre> <p>Copy the syntax from the Preview tab into your script.</p>
See also	<p>GetConnectionOption ReleaseConnectionOption UseContextObject</p>

## CallEscape

**Description** Controls whether the ODBC interface uses call escape syntax for stored procedure calls (the default) or converts the calls to driver-specific native SQL syntax before sending the command to the ODBC driver.

**Applies to** ODBC (if driver and back-end DBMS support this feature)

**Syntax** `CallEscape='value'`

Parameter	Description
<i>value</i>	<p>Controls whether the ODBC interface uses call escape syntax for stored procedure calls or converts the calls to driver-specific native SQL syntax. Values are:</p> <ul style="list-style-type: none"> <li>• <b>Yes</b> (Default) The ODBC interface uses call escape syntax for stored procedure calls</li> <li>• <b>No</b> The ODBC interface converts stored procedure calls to driver-specific native SQL syntax before sending the command to the ODBC driver</li> </ul>

**Default value** CallEscape = 'Yes'

**Usage** *When to use* Set CallEscape to No if the ODBC driver you are using expects to receive stored procedure calls in native (driver-specific) SQL syntax instead of in call escape syntax.

For information about the stored procedure call syntax your ODBC driver expects, see your vendor’s driver documentation.

*Level 2 or higher ODBC driver required* To use the CallEscape parameter, your ODBC driver *must* meet Level 2 or higher API conformance requirements. CallEscape has no effect when you are using an ODBC driver that meets Core or Level 1 API conformance requirements.

*Example of stored procedure call escape syntax* The following example shows a call to a stored procedure named sp\_test that uses call escape syntax:

```
{call sp_test(1,1)}
```

**Examples** To convert stored procedure calls to native SQL syntax before sending the command to your ODBC driver:

- **Database profile** Clear the Use Call Escape Syntax check box on the Syntax tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "CallEscape='No' "
```

## CharSet

**Description** Specifies the character set you want the Sybase Open Client™ software to use when connecting to a Sybase Adaptive Server Enterprise database or a database accessed through DirectConnect.

---

### When to specify CharSet

You must specify the CharSet parameter *before* connecting to a database.

---

**Applies to** DIR Sybase DirectConnect  
SYC Sybase Adaptive Server Enterprise

**Syntax** `CharSet = 'character_set'`

**Default value** None

**Usage** When you specify a value for CharSet, PowerBuilder:

- Allocates a CS\_LOCALE structure for this connection
- Sets the CS\_SYB\_CHARSET value to the character set you specify
- Sets the SQL Server CS\_LOC\_PROP connection property with the new locale information

*Overriding the Locale parameter* If you have previously set a value for the Locale parameter that includes settings for the language and character set you want to use, you can override the character set value by specifying a new value for the CharSet parameter and reconnecting to the database.

*Unicode data access* PowerBuilder can access Unicode data in an Adaptive Server Enterprise (ASE) 12.5 or later Unicode database or in Unicode columns in ASE 12.5 or later. PowerBuilder converts between double-byte character set (DBCS) data and Unicode automatically, provided that the CharSet and Language parameters are set with DBCS values (or the Locale parameter is set with DBCS values). For example:

```
CharSet = 'big5'
Language = 'tchinese'
```

**Examples** To set the character set to iso\_1:

- **Database profile** Type the following in the Character Set box on the Connection tab or Regional Settings tab in the Database Profile Setup dialog box:

```
iso_1
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "CharSet='iso_1'"
```

See also

Language  
Locale

## CnnPool

Description

Specifies whether Oracle should maintain connections in a pool. An Oracle connection pool is a group of reusable physical connections spanning several sessions and managed by the Oracle Call Interface (OCI). The CnnPool parameter cannot be used for PowerBuilder components deployed to EAServer, and external users cannot participate in a connection pool. By default, connection pooling is not used.

Applies to

O90 Oracle9i  
O10 Oracle 10g

Syntax

**CnnPool** = '*value*'

Parameter	Description
<i>value</i>	Values are: <ul style="list-style-type: none"> <li>• Yes</li> <li>• No (Default)</li> </ul>

Default value

No

Usage

If CnnPool='Yes', the Oracle9i or Oracle 10g client creates a connection pool and can connect to Oracle 8, Oracle8i, Oracle9i, and Oracle 10g Server. The pool contains physical connections to Oracle Server and is managed by the OCI. The pool persists until PowerBuilder terminates or *OCI.dll* is unloaded.

The DataWindow server can connect to 10 different Oracle servers, as distinguished by service name, concurrently. There can be no more than 20 connections per pool. Each pool is created by the Oracle9i or later client and might also contain connections to Oracle8 and Oracle8i servers. Once a connection pool has been created, PowerBuilder maintains the physical connections until it terminates or OCI.DLL is unloaded.

Examples

To use connection pooling:

- **Database profile** Enter values in the following fields of the Connection tab in the Database Profile Setup dialog box:
  - *Profile Name* – Example value: 08i-pool

- *Server* – Provide the full net service name created by Oracle Net. Example value: `adcora8i.sybase.com`
- *Login ID* – Example value: `scott`
- *Password*
- *Connect as* – Choose an item from the drop-down menu. Example value: `Normal`

Make sure Use Connection Pool is selected.

- **Application** Type the following in code where *password*, *server\_name*, and *login* are the appropriate values for your connection:

```
SQLCA.DBMS = "O90 Oracle9i (9.0.1)"
SQLCA.LogPass = <password>
SQLCA.ServerName = "server_name"
SQLCA.LogId = "login"
```

```
SQLCA.AutoCommit = False
SQLCA.DBParm = "CnnPool='Yes' "
```

## CommandTimeout

**Description** Specifies the number of seconds the interface should wait for a command to execute.

### When to specify CommandTimeout

You must specify a value for *CommandTimeout* *before* connecting to the database.

**Applies to** ADO.NET

**Syntax** `CommandTimeout = value`

Parameter	Description
<i>value</i>	The number of seconds the interface waits for a command to execute.

**Default value** None

**Usage** The default value for the *CommandTimeout* parameter is driver-specific.

- Examples To set the CommandTimeout value to wait 60 seconds for a command to execute:
- **Database profile** Type 60 in the Command Timeout box on the System tab in the Database Profile Setup dialog box.
  - **Application** Type the following in code:  

```
SQLCA.DBParm = "CommandTimeout=60"
```

## CommitOnDisconnect

Description Specifies whether PowerBuilder should commit (the default) or roll back all previously uncommitted database updates before disconnecting from a data source.

---

### When to specify CommitOnDisconnect

You must specify a value for CommitOnDisconnect *before* connecting to the database.

---

Applies to All database interfaces except SYJ

Syntax **CommitOnDisconnect** = '*value*'

Parameter	Description
<i>value</i>	<p>Specifies whether PowerBuilder should commit or roll back all previously uncommitted database updates before disconnecting from a data source. Values are:</p> <ul style="list-style-type: none"><li>• <b>Yes</b> (Default) PowerBuilder commits all uncommitted database updates when an application closes or when an explicit DISCONNECT statement is issued in code.</li><li>• <b>No</b> PowerBuilder rolls back all uncommitted database updates when an application closes or when an explicit DISCONNECT statement is issued in code. With this setting, PowerBuilder does not automatically commit updates when you disconnect from the database.</li></ul>

Default value CommitOnDisconnect = 'Yes'

Usage Set CommitOnDisconnect to No if you want PowerBuilder to roll back uncommitted database updates (instead of automatically committing them when you disconnect from the database).

**Examples** To tell PowerBuilder to roll back uncommitted database updates instead of committing them when disconnecting from the database:

- **Database profile** Clear the Commit On Disconnect check box on the Connection tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "CommitOnDisconnect='No' "
```

## ConnectAs

**Description** Allows the user to connect to the Oracle Server with SYSOPER or SYSDBA system privileges.

**Applies to** O90 Oracle9i  
O10 Oracle 10g

**Syntax** **ConnectAs = 'value'**

Parameter	Description
<i>value</i>	Values are: <ul style="list-style-type: none"> <li>• SYSDBA</li> <li>• SYSOPER</li> <li>• Normal (Default)</li> </ul>

**Default value** Normal

**Usage** If `ConnectAs = 'Normal'`, this parameter is not used. If `ConnectAs = 'SYSDBA'` or `ConnectAs = 'SYSOPER'`, Oracle9i or later allows the user to connect with SYSDBA or SYSOPER privileges, respectively, provided that these privileges have been granted the user.

If you connect using `ConnectAs = 'SYSDBA'`, Oracle9i or later uses the SYS schema instead of the schema that might already be associated with the user ID. If you connect using `ConnectAs = 'SYSOPER'`, Oracle9i or later uses the PUBLIC schema.

---

### **Do not use with CnnPool = 'Yes'**

Connection pooling cannot be used with this parameter. Do not select Use Connection Pool in the Database Profile Setup dialog box or set CnnPool to 'Yes'.

---

- Examples
- To use the SYS schema instead of the schema associated with the User ID:
- **Database profile** Select SYSDBA from the Connect As drop-down list on the Connection page in the Database Profile Setup dialog box, and make sure Use Connection Pool is deselected.
  - **Application** Type the following in code:

```
SQLCA.DBParm = "ConnectAs='SYSDBA' "
```

## ConnectOption

Description

Sets driver-specific connection options when you are accessing an ODBC data source in PowerBuilder. These options specify the following:

- How the ODBC driver prompts for additional connection information
- What type of security to use for a Microsoft SQL Server connection
- Whether the ODBC Driver Manager Trace is on or off and what trace file it uses
- Whether cursors are closed or left open on a SQLTransact call
- How temporary stored procedures are treated for a SQLPrepare call

Certain ConnectOption parameters apply to all ODBC drivers, whereas others apply only to particular ODBC drivers.

For information on each ConnectOption parameter and whether you can use it with your ODBC driver, see the table in the Syntax section.

---

### When to specify ConnectOption

You must specify the ConnectOption parameter *before* connecting to an ODBC data source. The ConnectOption settings take effect when you connect to the database.

---

Applies to

ODBC (if driver and back-end DBMS support this feature)

Syntax

```
ConnectOption = ' SQL_DRIVER_CONNECT,value;  
SQL_INTEGRATED_SECURITY,value;  
SQL_OPT_TRACE,value;  
SQL_OPT_TRACEFILE,value;  
SQL_PRESERVE_CURSORS,value;  
SQL_USE_PROCEDURE_FOR_PREPARE,value '
```



The following table lists the applicable ODBC drivers, purpose, and values for each ConnectOption parameter.

Parameter	Description
SQL_DRIVER_CONNECT	<p><b>Driver</b> Any ODBC driver that supports the SQLDriverConnect API call.</p> <p><b>Purpose</b> Specifies how the ODBC driver prompts for additional connection information (such as the user ID and password) when connecting to an ODBC data source.</p> <p><b>Values</b> The values you can specify are:</p> <ul style="list-style-type: none"> <li>• <b>SQL_DRIVER_COMPLETE</b> (Default) If the connection string contains correct and sufficient information to connect, the driver connects to the specified data source. If any information is incorrect or missing, the driver displays one or more dialog boxes to prompt for the required connection parameters. The driver then connects to the specified data source.</li> <li>• <b>SQL_DRIVER_COMPLETE_REQUIRED</b> The driver takes the same actions as it does when SQL_DRIVER_COMPLETE is set. In addition, the driver disables the controls for any information not required to connect to the data source.</li> <li>• <b>SQL_DRIVER_PROMPT</b> The driver displays one or more dialog boxes to prompt for the required connection parameters. The driver then connects to the specified data source and builds a connection string from the information specified in the dialog boxes.</li> <li>• <b>SQL_DRIVER_NOPROMPT</b> If the connection string contains correct and sufficient information to connect, the driver connects to the specified data source. If any information is incorrect or missing, the driver returns an error.</li> </ul>
SQL_INTEGRATED_SECURITY	<p><b>Driver</b> Microsoft SQL Server ODBC driver (not supplied with PowerBuilder).</p> <p><b>Purpose</b> Specifies the type of connection to the Microsoft SQL Server database server.</p> <p><b>Values</b> The values you can specify are:</p> <ul style="list-style-type: none"> <li>• <b>SQL_IS_OFF</b> (Default) Request a normal (nontrusted) connection to SQL Server using standard security. If you specify SQL_IS_OFF, you cannot request a trusted connection to SQL Server using integrated security.</li> <li>• <b>SQL_IS_ON</b> Request a trusted connection to SQL Server using integrated security regardless of the login security currently in use on the database server.</li> </ul> <p>For more about security mechanisms in Microsoft SQL Server, see the Microsoft documentation.</p>

Parameter	Description
SQL_OPT_TRACE	<p><b>Driver</b> Any ODBC driver.</p> <p><b>Purpose</b> Turns on or turns off the ODBC Driver Manager Trace in PowerBuilder to troubleshoot a connection to an ODBC data source. The ODBC Driver Manager Trace provides detailed information about the ODBC API function calls that PowerBuilder makes when connected to an ODBC data source.</p> <p><b>Values</b> The values you can specify are:</p> <ul style="list-style-type: none"> <li>• <b>SQL_OPT_TRACE_OFF</b> (Default) Turns off the ODBC Driver Manager Trace.</li> <li>• <b>SQL_OPT_TRACE_ON</b> Turns on the ODBC Driver Manager Trace.</li> </ul> <p>For instructions on using the ODBC Driver Manager Trace, see “About ODBC Driver Manager” in <i>Connecting to Your Database</i>.</p>
SQL_OPT_TRACEFILE	<p><b>Driver</b> Any ODBC driver.</p> <p><b>Purpose</b> Specifies the name of the trace file where you want PowerBuilder to send the output of the ODBC Driver Manager Trace. PowerBuilder appends the output to the trace file you specify until you stop the trace. To display the trace file, you can use the File Editor (in PowerBuilder) or any text editor (outside PowerBuilder).</p> <p><b>Values</b> You can specify any filename for the trace file, following the naming conventions of your operating system. By default, if tracing is on and you have not specified a trace file, PowerBuilder sends ODBC Driver Manager Trace output to the file \SQL.LOG.</p>
SQL_PRESERVE_CURSORS	<p><b>Driver</b> Microsoft SQL Server ODBC driver (not supplied with PowerBuilder).</p> <p><b>Purpose</b> Specifies whether cursors are closed or left open on a SQLTransact call.</p> <p><b>Values</b> The values you can specify are:</p> <ul style="list-style-type: none"> <li>• <b>SQL_PC_OFF</b> (Default) Close all cursors on a SQLTransact call.</li> <li>• <b>SQL_PC_ON</b> Keep server cursors open on a SQLTransact call.</li> </ul>

Parameter	Description														
SQL_USE_PROCEDURE_FOR_PREPARE	<p><b>Driver</b> Microsoft SQL Server ODBC driver (not supplied with PowerBuilder).</p> <p><b>Purpose</b> Specifies how temporary stored procedures are treated for a SQLPrepare call.</p> <p><b>Values</b> The values you can specify are:</p> <ul style="list-style-type: none"> <li>• <b>SQL_UP_ON</b> (Default) Generate temporary stored procedures for a SQLPrepare call.</li> <li>• <b>SQL_UP_OFF</b> Do not generate temporary stored procedures for a SQLPrepare call. The SQL statement is stored, compiled, and run at execution time. Syntax error checking does not occur until execution time.</li> <li>• <b>SQL_UP_ON_DROP</b> Explicitly drop temporary stored procedures for a subsequent SQLPrepare call or when a statement handle (hstmt) is freed for reuse.</li> </ul>														
Default value	ConnectOption = 'SQL_DRIVER_CONNECT, SQL_DRIVER_COMPLETE; SQL_INTEGRATED_SECURITY, SQL_IS_OFF; SQL_OPT_TRACE, SQL_OPT_TRACE_OFF; SQL_PRESERVE_CURSORS, SQL_PC_OFF; SQL_USE_PROCEDURE_FOR_PREPARE, SQL_UP_ON'														
Usage	<p><i>Microsoft Server ODBC driver</i> The ConnectOption parameter applies only if you are accessing a SQL Server database with the Microsoft ODBC SQL Server driver.</p> <p>You must obtain the Microsoft SQL Server ODBC driver from Microsoft Corporation. This driver is <i>not</i> supplied with PowerBuilder.</p>														
Examples	<p>To specify nondefault options for the ConnectOption parameter:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Complete the Options tab in the Database Profile Setup - ODBC dialog box. Each ConnectOption parameter corresponds to an option in the dialog box, as follows:</li> </ul> <table border="1"> <thead> <tr> <th>ConnectOption parameter</th> <th>Corresponding option</th> </tr> </thead> <tbody> <tr> <td>SQL_DRIVER_CONNECT</td> <td>Connect Type</td> </tr> <tr> <td>SQL_INTEGRATED_SECURITY</td> <td>Integrated Security</td> </tr> <tr> <td>SQL_OPT_TRACE</td> <td>Trace ODBC API Calls</td> </tr> <tr> <td>SQL_OPT_TRACEFILE</td> <td>Trace File</td> </tr> <tr> <td>SQL_PRESERVE_CURSORS</td> <td>Preserve Cursors</td> </tr> <tr> <td>SQL_USE_PROCEDURE_FOR_PREPARE</td> <td>Use Procedure for Prepare</td> </tr> </tbody> </table>	ConnectOption parameter	Corresponding option	SQL_DRIVER_CONNECT	Connect Type	SQL_INTEGRATED_SECURITY	Integrated Security	SQL_OPT_TRACE	Trace ODBC API Calls	SQL_OPT_TRACEFILE	Trace File	SQL_PRESERVE_CURSORS	Preserve Cursors	SQL_USE_PROCEDURE_FOR_PREPARE	Use Procedure for Prepare
ConnectOption parameter	Corresponding option														
SQL_DRIVER_CONNECT	Connect Type														
SQL_INTEGRATED_SECURITY	Integrated Security														
SQL_OPT_TRACE	Trace ODBC API Calls														
SQL_OPT_TRACEFILE	Trace File														
SQL_PRESERVE_CURSORS	Preserve Cursors														
SQL_USE_PROCEDURE_FOR_PREPARE	Use Procedure for Prepare														

- **Application** Type the following in code:

```
SQLCA.DBParm = "ConnectOption =
    'SQL_DRIVER_CONNECT,SQL_DRIVER_NOPROMPT;
    SQL_INTEGRATED_SECURITY,SQL_IS_ON;
    SQL_OPT_TRACE,SQL_OPT_TRACE_ON;
    SQL_OPT_TRACEFILE,C:\PB\odbctrce.log;
    SQL_PRESERVE_CURSORS,SQL_PC_ON;
    SQL_USE_PROCEDURE_FOR_PREPARE,SQL_UP_OFF' "
```

## ConnectionString

**Description** Specifies the parameters required to connect to an ODBC data source. PowerBuilder uses these parameters to connect to the database.

**Applies to** ODBC

**Syntax** The ConnectString syntax displays on a single line. You must enclose the entire ConnectString in single quotes and separate parameters within the ConnectString with semicolons.

```
ConnectString = 'DSN = data_source_name; {UID = user_ID;  
                PWD = password; driver_specific_parameters'
```

Parameter	Description
<i>data_source_name</i>	A name that identifies the data source.
<i>user_ID</i>	(Optional) The user ID required to connect to the data source.
<i>password</i>	(Optional) The password required by <i>user_ID</i> to connect to the data source.
<i>driver_specific_parameters</i>	(Optional) Any other driver-specific parameters required to connect.  For example, some ODBC drivers specify the data source directory here. If you are using the PB DataDirect Btrieve ODBC driver, you can specify the value <code>CDB = 1</code> here to create a new Scalable SQL (formerly NetWare SQL) data dictionary if one does not already exist.  The PB DataDirect Text ODBC driver uses this parameter to specify the century date. You can specify the value <code>CB = 50</code> here to indicate that years from 00 to 49 be prefixed with '20' and years from 50 to 99 be prefixed with '19'.

Default value	None
Usage	<p>PowerBuilder generates the <code>ConnectionString</code> automatically when you define an ODBC data source and copies it to the Preview box in the Database Profile Setup dialog box. This happens before you connect to the data source in PowerBuilder.</p> <p>Therefore, <i>you do not have to enter the <code>ConnectionString</code> yourself</i> when defining an ODBC data source. However, you might need to edit the <code>ConnectionString</code> value in the Database Profile Setup dialog box.</p> <p>You can change the <code>ConnectionString</code> parameter if necessary by editing it in the Database Profile Setup dialog box. For example, if you change the name of an existing ODBC data source, edit its database profile to update the connect string with the new DSN (data source name) value.</p>
Examples	<p><b>Example 1</b> This example shows a connect string for an ODBC data source that contains the data source name (<code>DSN=Sales</code>), user ID (<code>UID=dba</code>), and password (<code>PWD=sql</code>). Parameters within the connect string are separated by semicolons.</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> On the Connection tab in the Database Profile Setup dialog box, select Sales from the Data Source drop-down list, select the User ID check box and type dba, and select the Password check box and type sql.</li> <li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm = "ConnectionString = 'DSN=Sales;UID=dba; PWD=sql' "</pre> </li> </ul> <p><b>Example 2</b> This example shows a connect string for a Btrieve data source accessed with the PB DataDirect Btrieve ODBC driver. The connect string consists of two parameters: DSN and CDB (to create a new Scalable SQL data dictionary). Parameters within the connect string are separated by semicolons.</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Select Btrieve from the DataSource drop-down list box on the Connection tab in the Database Profile Setup dialog box, and type the following in the Driver-Specific Parameters box: <pre>CDB=1</pre> </li> <li>• <b>Application</b> To specify this statement in code, type the following: <pre>SQLCA.DBParm = "ConnectionString = 'DSN=Btrieve;CDB=1' "</pre> </li> </ul> <hr/> <p><b>Adding Parameters</b> If the DSN appears in the drop-down list, it is not necessary to add it to the parameters.</p> <hr/>

## CursorLib

Description	Specifies the cursor library to use when connecting to an ODBC data source.
Applies to	ODBC (if driver and back-end DBMS support this feature)
Syntax	<b>CursorLib</b> = ' <i>value</i> '

Parameter	Description
<i>value</i>	<p>The cursor library to use when connecting to an ODBC data source. Values are:</p> <ul style="list-style-type: none"> <li>• <b>ODBC_Cur_Lib</b> Use the ODBC Version 2.0 or higher cursor library.</li> <li>• <b>If_Needed</b> Use the ODBC Version 2.0 or higher cursor library if your ODBC driver does not support cursors.</li> <li>• <b>Driver_Cursors</b> (Default) Use your data source's native cursor support.</li> </ul>

Default value      CursorLib = 'Driver\_Cursors'

Examples      To specify use of the ODBC Version 2.0 or higher cursor library when connecting to an ODBC data source:

- **Database profile** Select Cursor Library from the Cursor Library drop-down list on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "CursorLib='ODBC_Cur_Lib' "
```

## CursorLock

Description	<p>When used with the CursorScroll parameter, specifies locking options for cursors in ODBC data source.</p> <p>The values you can set for CursorLock control two aspects of cursor locking:</p> <ul style="list-style-type: none"> <li>• <b>Concurrent access</b> Ensures that multiple users can simultaneously access data that is accurate and current.</li> <li>• <b>Collision detection</b> Detects collisions that occur when multiple users update the same data at the same time.</li> </ul>
Applies to	ODBC (if driver and back-end DBMS support this feature)

Syntax

**CursorLock** = 'lock\_value'

Parameter	Description
<i>lock_value</i>	<p>Specifies the type of locking you want to use for ODBC cursors. Values are:</p> <ul style="list-style-type: none"> <li>• <b>Lock</b> Use the lowest level of locking sufficient to allow updates on table rows.</li> <li>• <b>Opt</b> Use <b>optimistic concurrency control</b>. This means that table rows are not locked against updates by other users. To detect collisions, compare row versions or timestamps.</li> <li>• <b>OptVal</b> Use optimistic concurrency control. This means that table rows are not locked against updates by other users. To detect collisions, compare selected values with their previous values.</li> <li>• <b>ReadOnly</b> Prohibit updates on table rows by any user.</li> </ul> <p>For more about how the ODBC standard defines lock values, see your ODBC documentation.</p>

Default value

If you do not specify a value for CursorLock, PowerBuilder defaults to the cursor lock setting specified by your ODBC driver.

Examples

To set scrolling and locking options for cursors in an ODBC data source:

- **Database profile** On the Transaction tab in the Database Profile Setup dialog box, select Dynamic Scrolling from the Scrolling Options drop-down list, and Optimistic Using Values from the Locking drop-down list.
- **Application** Type the following in code:

```
SQLCA.DBParm =
    "CursorScroll='Dynamic',CursorLock='OptVal' "
```

See also

CursorScroll

## CursorScroll

Description

When used with the CursorLock parameter, specifies scrolling options for cursors in an ODBC data source.

The location of a cursor indicates the current position in the result set produced by a SQL statement. **Scrolling** allows a cursor to move through the data in a result set one row at a time.

Applies to

ODBC (if driver and back-end DBMS support this feature)

Syntax

**CursorScroll** = 'scroll\_value'

Parameter	Description
<i>scroll_value</i>	<p>Specifies the type of scrolling you want to use for ODBC cursors. Values are:</p> <ul style="list-style-type: none"> <li>• <b>Forward</b> The cursor only scrolls forward through the result set.</li> <li>• <b>Static</b> The data in the result set does not change.</li> <li>• <b>KeySet</b> Specifies that the cursor is <b>keyset-driven</b>. When a keyset-driven cursor is opened, the driver saves keys for the <i>entire result set</i>. As the cursor scrolls through the result set, the driver uses the keys in this <b>keyset</b> to retrieve the current values for each row.</li> <li>• <b>Dynamic</b> The driver saves and uses only the keys for the rows specified in the rowset.</li> </ul>

Default value

If you do not specify a value for CursorScroll, PowerBuilder defaults to the cursor scroll settings specified for your ODBC data source driver.

Usage

For large result sets, it might be impractical to use a keyset-driven cursor that requires the driver to save keys for the entire result set. Instead, you can use a **mixed cursor** by specifying a 32-bit integer value that is the number of rows in your keyset (see Example 2). This number is typically smaller than the result set. The default keyset size is 0.

A mixed cursor uses KeySet scrolling within the specified keyset and Dynamic scrolling outside the keyset.

Examples

**Example 1** To set scrolling and locking options for cursors in an ODBC data source:

- **Database profile** Select Dynamic Scrolling from the Scrolling Options drop-down list and Optimistic Using Values from the Locking drop-down list on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm =
    "CursorScroll='Dynamic',CursorLock='OptValue' "
```

**Example 2** This example sets the number of rows in the keyset to 100. Assume that the entire result set has 1000 rows. When the cursor is opened, the driver saves keys for the first 100 rows of the result set. It then retrieves the next block of 100 keys until the entire result set is retrieved.

- **Database profile** Type 100 in the Scrolling Options box on the Transaction tab in the Database Profile Setup dialog box.



- **Application** Type the following in code:

```
SQLCA.DBParm = "CursorScroll=100"
```

See also

CursorLock

## CursorType

Description

Supports the scrollable cursor feature introduced in Adaptive Server Enterprise 15.0, including directional scrolling (forwards and backwards) and sensitivity towards independent changes to table.

Applies to

SYC Sybase Adaptive Server Enterprise (15.0 and later)

Syntax

**CursorType** = *value*

Parameter	Description
<i>value</i>	<p>A string that specifies whether database cursors are scrollable and whether they are sensitive to modifications in data. Values are:</p> <ul style="list-style-type: none"> <li>• <b>NonScrollable</b> (Default) Non-scrollable forward-only cursor. Supports the PowerScript FETCH NEXT syntax.</li> <li>• <b>ScrollInsensitive</b> Scrollable insensitive cursor that ignores any data modifications when scrolling in either direction. Supports the PowerScript FETCH NEXT, FETCH PRIOR, FETCH FIRST, and FETCH LAST syntaxes.</li> <li>• <b>ScrollSemiSensitive</b> Scrollable semi-sensitive cursor that presents data modifications when scrolling forwards but ignores them when scrolling backwards. Supports the PowerScript FETCH NEXT, FETCH PRIOR, FETCH FIRST, and FETCH LAST syntaxes.</li> </ul>

Default value

CursorType='NonScrollable'

Usage

Adaptive Server Enterprise 15.0 allows both scrollable and nonscrollable cursors, which can be either semi-sensitive or insensitive. “Scrollable” means that you can scroll through the cursor result set by fetching any, or many, rows, rather than one row at a time; you can also scan the result set repeatedly. A scrollable cursor allows you to set the position of the cursor anywhere in the cursor result set for as long as the cursor is open.

To use a scrollable cursor, you must use a DECLARE *CursorName* CURSOR SQL statement to declare it with a suitable SELECT statement and y, such as the PowerBuilder Dynamic SQL Format 3 and Dynamic SQL Format 4 statementsou must have the query engine provided in Adaptive Server 15.0 or later.

For sensitive scrolling to work correctly, the table must have a clustered index or a clustered unique constraint, such as a clustered primary key.

All scrollable cursors are read-only and can only be used when the value of the CursorUpdate database parameter is 0 (the default). If you need an updatable cursor, set the CursorUpdate parameter to 1. When CursorUpdate is set to 1, the value of CursorType is ignored. All update cursors are nonscrollable.

If a scrollable cursor is moved to a position before the first row or after the last row, `SQLCA.SQLCode` returns 100 and no data is returned. However, users can continue to fetch data by using a suitable `FETCH` statement after receiving this `SQLCode` value.

Both client and server must be Adaptive Server 15.0 or higher.

Examples

To specify support for semi-sensitive scrollable cursors (data modifications are presented when scrolling forwards):

- **Database profile** Select Cursor Scrollable SemiSensitive from the Read Only Cursor Type drop-down list on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "CursorType=ScrollSemiSensitive"
```

See also

CursorUpdate

## CursorUpdate

Description

For those interfaces that support it, CursorUpdate specifies whether cursors in your target database are declared read-only or updatable.

Applies to

DIR Sybase DirectConnect  
 SYC and SYJ Sybase Adaptive Server Enterprise

Syntax

**CursorUpdate** = *value*

Parameter	Description
<i>value</i>	A number that specifies whether database cursors are declared read-only or updatable. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Cursors are declared read-only. Sybase Client Library cursor declarations include the <code>CS_READ_ONLY</code> option.</li> <li>• <b>1</b> Cursors are declared updatable. Sybase Client Library cursor declarations include the <code>CS_FOR_UPDATE</code> option. This option applies to all updatable columns in the table.</li> </ul>

Default value	CursorUpdate = 0
Usage	<p>Set the CursorUpdate parameter to 1 to declare updatable cursors if you plan to use either of the following SQL statements in your application (<i>table</i> represents the table name and <i>cursor</i> represents the cursor name):</p> <pre><b>DELETE FROM</b> <i>table</i> <b>WHERE CURRENT OF</b> <i>cursor</i> <b>UPDATE</b> <i>table</i> <b>SET</b> <i>set_clause</i> <b>WHERE CURRENT OF</b> <i>cursor</i></pre> <p>If you are communicating with the database in a PowerBuilder script, you can reset the CursorUpdate value anytime before or after the Transaction object has connected to the database.</p> <p>When you declare cursors updatable in a database accessed through DirectConnect, the cursor declaration you code must include a FOR UPDATE OF <i>column_list</i> clause.</p> <p>When you use updatable cursors with the DIR interface and a Gatewayless connection to the mainframe, you must set Block = 1 before executing the cursor. You can reset the Block parameter to its default of 100 after you close the cursor within your code.</p>
Examples	<p>To specify that database cursors are declared updatable:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Select the Cursors Declared Updatable check box on the Transaction tab in the Database Profile Setup dialog box.</li> <li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm = "CursorUpdate=1"</pre> </li> </ul>

## Database

Description	Specifies the name of the database you want to connect to.
	<hr/> <p><b>When to specify Database</b> You must specify the Database parameter <i>before</i> connecting to the database.</p> <hr/>
Applies to	ADO.NET
Syntax	<b>DataBase</b> = ' <i>database_name</i> '
Default value	None
Examples	<p>To connect to the database “mydb”:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Enter mydb in the Database box on the Connection page in the Database Profile Setup dialog box.</li> </ul>

- **Application** Type the following in code:

```
SQLCA.DBParm = "Database='mydb' "
```

## DataLink

### Description

Specifies that you want to create a file or use an existing file containing your connection information to connect to your data source.

---

### When to specify DataLink

You must specify the DataLink parameter *before* connecting to the database.

---

### Applies to

ADO.NET  
OLE DB

### Syntax

**DataLink** = '*file\_name*'

### Default value

None

### Usage

The Data Link option allows you to access Microsoft's Data Link API. The Data Link API allows you to define a file or use an existing file that contains your OLE DB connection information. A Data Link file is identified with the suffix *.udl*.

To launch the API, double-click on Manage Data Links under OLE DB Utilities in the Installed Database Interfaces list or select the File Name check box on the Connection tab in the Database Profile Setup dialog box and double-click on the button next to the File Name box.

For more information on using the Data Link API, see Microsoft's Universal Data Access Web site.

---

### Using a Data Link file versus setting the database parameters

If you use a Data Link file to connect to your data source, all other settings you make in the Database Profile Setup dialog box are ignored.

---

### Examples

To use the file *oledb.udl* to connect to an OLE DB data provider:

- **Database profile** Select the File Name check box on the Connection tab in the Database Profile Setup dialog box and enter a name for a new file or select an existing file.
- **Application** Type the following in code:

```
SQLCA.DBParm = "DataLink='oledb.udl' "
```

## DataSource

**Description** Identifies the data source to which you want to connect. The data source can be a file, a database, or an ODBC data source depending on the OLE DB data provider you are using.

---

### When to specify DataSource

You must specify the DataSource parameter *before* connecting to the database.

---

<b>Applies to</b>	ADO.NET OLE DB
<b>Syntax</b>	<b>DataSource</b> = ' <i>datasource_name</i> '
<b>Default value</b>	None
<b>Usage</b>	<p>The value of the Data Source parameter varies depending on the type of data source connection you are making. For example, if you are using Microsoft's OLE DB Provider for ODBC, you would enter the actual ODBC data source name for the Data Source value. If you are using Microsoft's OLE DB Provider for SQL Server, you would enter the actual Microsoft SQL Server server name for the Data Source value.</p> <p>For more information, see the documentation provided by your OLE DB data provider.</p>
<b>Examples</b>	<p><b>Example 1</b> To use the Microsoft OLE DB Provider for ODBC to connect to the EAS Demo DB:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Enter EAS Demo DB in the Data Source box on the Connection tab in the Database Profile Setup dialog box.</li> <li>• <b>Application</b> Type the following in code:           <pre>SQLCA.DBParm = "DataSource='EAS Demo DB'"</pre> </li> </ul> <p><b>Example 2</b> To use the PB DataDirect OLE DB Provider to connect to an Oracle 8 database:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Enter the data source name in the Data Source box on the Connection tab in the Database Profile Setup dialog box. You should have previously defined the data source name using the PB DataDirect OLE DB Administrator.</li> <li>• <b>Application</b> Type the following in code:           <pre>SQLCA.DBParm = "DataSource='Oracle8'"</pre> </li> </ul>

**Example 3** To use the Microsoft OLE DB Provider for Oracle to connect to an Oracle 8 database:

- **Database profile** Enter the Oracle 8 server name in the Data Source box on the Connection tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "DataSource='Or8server' "
```

See also

DataLink  
Provider

## Date

Description

When you update data in the DataWindow painter, PowerBuilder builds a SQL UPDATE statement in the background. The Date parameter determines how PowerBuilder specifies a date datatype when it builds the SQL UPDATE statement.

Applies to

JDB JDBC  
ODBC  
O84 Oracle 8.x and Oracle8i  
O90 Oracle9i  
O10 Oracle 10g

Syntax

The syntax you use to specify the Date parameter differs slightly depending on the database.

The Database Profile Setup dialog box inserts special characters (quotes and backslashes) where needed, so you can specify just the date format.

In a PowerBuilder application script, you must use the following syntax:

**JDBC and ODBC syntax** PowerBuilder parses the backslash followed by two single quotes (\ ' ') as a single quote when it builds the SQL UPDATE statement.

```
Date = '\ 'date_format' '
```

**Oracle syntax** PowerBuilder parses each set of four consecutive single quotes ( ' ' ' ' ) as a single quote when it builds the SQL UPDATE statement.

**Date = ' ""date\_format"" '**

Parameter	Description
' \"	<b>JDBC and ODBC syntax</b> Type a single quote, followed by one space, followed by a backslash, followed by two single quotes. There is no space between the two single quotes and the beginning of the date format.
' ""	<b>Oracle syntax</b> Type a single quote, followed by one space, followed by four single quotes. There is no space between the four single quotes and the beginning of the date format.
<i>date_format</i>	The date format you want PowerBuilder to use when it builds a SQL UPDATE statement to update a data source in the DataWindow painter. For more on display formats, see the <i>User's Guide</i> .
\"'	<b>JDBC and ODBC syntax</b> Type a backslash, followed by two single quotes, followed by one space, followed by a single quote. There is no space between the end of the date format and the backslash.
""'	<b>Oracle syntax</b> Type four single quotes, followed by one space, followed by a single quote. There is no space between the end of the date format and the four single quotes.

Default value

The default value for Date depends on the DBMS you are accessing, as summarized in the following table:

DBMS	Date default value
JDBC	If no value is specified for the Date database parameter, PowerBuilder looks for a date format in the section for your JDBC driver in the registry. If no date format is found in the registry, PowerBuilder uses the JDBC date format escape sequence.
ODBC	If no value is specified for the Date database parameter, PowerBuilder looks for a date format in the section for your ODBC driver in the PBODB105 initialization file. If no date format is found in the initialization file, PowerBuilder uses the ODBC date format escape sequence.
Oracle	The default Oracle date format. For information, see your Oracle documentation.

Examples

**About these examples** Assume you are updating a table named Employee by setting the Startdate column to 2006-04-23. This date is represented by the following date format:

yyyy-mm-dd

**Example 1 (JDBC and ODBC syntax)** To specify that PowerBuilder should use this format for the date datatype when it builds the SQL UPDATE statement:

- **Database profile** Type the following in the Date Format box on the Syntax tab in the Database Profile Setup dialog box:

yyyy-mm-dd

- **Application** Type the following in code:

```
SQLCA.DBParm = "Date= ' \'yyyy-mm-dd\' ' ' "
```

*What happens* PowerBuilder builds the following SQL UPDATE statement to update the table:

```
UPDATE EMPLOYEE  
SET STARTDATE = '2006-04-23'
```

**Example 2 (Oracle syntax)** To specify that PowerBuilder should use this format for the date datatype when it builds the SQL UPDATE statement:

- **Database profile** Type the following in the Date format box on the Syntax tab in the Database Profile Setup dialog box:

yyyy-mm-dd

- **Application** Type the following in code:

```
SQLCA.DBParm = "Date= ' ' 'yyyy-mm-dd' ' ' ' "
```

*What happens* PowerBuilder builds the following SQL UPDATE statement to update the table:

```
UPDATE EMPLOYEE  
SET STARTDATE = '2006-04-23'
```

See also

DateTime  
Time



## DateFormat

**Description** When you update data in the DataWindow painter, PowerBuilder builds a SQL UPDATE statement in the background. The DateFormat parameter determines how PowerBuilder specifies a date datatype when it builds the SQL UPDATE statement.

**Applies to** ADO.NET  
OLE DB

**Syntax** `DateFormat = 'date_format'`

Parameter	Description
<code>date_format</code>	The date format you want PowerBuilder to use when it builds a SQL UPDATE statement to update a data source in the DataWindow painter. For more on display formats, see the <i>User's Guide</i> .

**Default value** If no value is specified for the DateFormat parameter, PowerBuilder does not use a date datatype.

**Usage** When you call stored procedures, the database server might not accept the date format built by PowerBuilder. If this occurs, you can try to use another format. For example, for Microsoft SQL Server, try this format:

```
DateFormat='\'\'yyyy-mm-dd\'\'\'
```

**Examples** Assume you are updating a table named Employee by setting the Startdate column to 2006-04-23. This date is represented by the date format `yyyy-mm-dd`.

To specify that PowerBuilder should use this format for the date datatype when it builds the SQL UPDATE statement:

- **Database profile** Type the following in the Date Format box on the Syntax tab in the Database Profile Setup dialog box:

```
yyyy-mm-dd
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "DateFormat='yyyy-mm-dd' "
```

*What happens* PowerBuilder builds the following SQL UPDATE statement to update the table:

```
UPDATE EMPLOYEE
SET STARTDATE = '2006-04-23'
```

**See also** DateTimeFormat  
TimeFormat

## DateTime

**Description** When you update data in the DataWindow painter, PowerBuilder builds a SQL UPDATE statement in the background. The DateTime parameter determines how PowerBuilder specifies a DateTime datatype when it builds the SQL UPDATE statement. (A DateTime datatype contains both a date value and a time value.)

**Applies to** JDB JDBC  
 ODBC  
 O84 Oracle 8.x and Oracle8i  
 O90 Oracle9i  
 O10 Oracle 10g

**Syntax** The syntax you use to specify the DateTime differs slightly depending on the database.

The Database Profile Setup dialog box inserts special characters (quotes and backslashes) where needed, so you can specify just the DateTime format.

In code, you must use the following syntax:

**JDBC and ODBC syntax** PowerBuilder parses the backslash followed by two single quotes (\') as a single quote when it builds the SQL UPDATE statement.

**DateTime** = ' \'DateTime\_format\''

**Oracle syntax** PowerBuilder parses each set of four consecutive single quotes ('''' ) as a single quote when it builds the SQL UPDATE statement.

**DateTime** = ' ''''DateTime\_format'''' '

Parameter	Description
' \'	<b>JDBC and ODBC syntax</b> Type a single quote, followed by one space, followed by a backslash, followed by two single quotes. There is no space between the two single quotes and the beginning of the DateTime format.
' ''''	<b>Oracle syntax</b> Type a single quote, followed by one space, followed by four single quotes. There is no space between the four single quotes and the beginning of the date format.
DateTime_format	The DateTime format you want PowerBuilder to use when it builds a SQL UPDATE statement to update a data source in the painter.  For more on display formats, see the <i>User's Guide</i> .

Parameter	Description
\''	<b>JDBC and ODBC syntax</b> Type a backslash, followed by two single quotes, followed by one space, followed by a single quote. There is no space between the end of the date format and the backslash.
''''	<b>Oracle syntax</b> Type four single quotes, followed by one space, followed by a single quote. There is no space between the end of the DateTime format and the four single quotes.

Default value

The default value for DateTime depends on the DBMS you are accessing, as summarized in the following table:

DBMS	Date default value
JDBC	If no value is specified for the DateTime database parameter, PowerBuilder looks for a DateTime format in the section for your JDBC driver in the registry. If no DateTime format is found in the registry, PowerBuilder uses the JDBC DateTime format escape sequence.
ODBC	If no value is specified for the DateTime database parameter, PowerBuilder looks for a DateTime format in the section for your ODBC driver in the <i>PBODB105</i> initialization file. If no DateTime format is found in the initialization file, PowerBuilder uses the ODBC DateTime format escape sequence.
Oracle	The default Oracle DateTime format. For information, see your Oracle documentation.

Examples

**About these examples** Assume you are updating a table named Files by setting the Timestamp column to 4/2/06 3:45 pm. This DateTime is represented by the following DateTime format:

```
m/d/yy h:mm am/pm
```

**Example 1 (JDBC, ODBC, and OLE DB syntax)** To specify that PowerBuilder should use this format for the DateTime datatype when it builds the SQL UPDATE statement:

- **Database profile** Type the following in the DateTime Format box on the Syntax tab in the Database Profile Setup dialog box:

```
m/d/yy h:mm am/pm
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "DateTime=' 'm/d/yy h:mm am/pm\'' ' "
```

*What happens* PowerBuilder builds the following SQL UPDATE statement to update the table:

```
UPDATE FILES
SET TIMESTAMP='4/2/06 3:45 pm'
```

**Example 2 (Oracle syntax)** To specify that PowerBuilder should use this format for the DateTime datatype when it builds the SQL UPDATE statement:

- **Database profile** Type the following in the DateTime Format box on the Syntax tab in the Database Profile Setup dialog box:

```
m/d/yy h:mm am/pm
```

- **Application** Type the following in code:

```
SQLCA.DBParm="DateTime=' ' 'm/d/yy h:mm am/pm' ' ' '
' "
```

*What happens* PowerBuilder builds the following SQL UPDATE statement to update the table:

```
UPDATE FILES
SET TIMESTAMP = '4/2/06 3:45 pm'
```

See also

Date  
Time

## DateTimeAllowed

### Description

For those interfaces that support it, DateTimeAllowed controls whether columns having a DateTime datatype can appear as unique key columns in the WHERE clause of a SQL UPDATE or DELETE statement. PowerBuilder generates an UPDATE statement or a DELETE statement followed by an INSERT statement to update the database from a DataWindow object.

When you are working in the DataWindow painter, you specify which columns to include in the WHERE clause by selecting them from the Unique Key Columns list in the Specify Update Properties dialog box.

By default, DateTimeAllowed is set to 0 to prohibit DateTime columns from displaying in the Unique Key Columns list and consequently from appearing in the WHERE clause of an UPDATE or DELETE statement. When you set DateTimeAllowed to 1, any DateTime columns in your database table display in the Unique Key Columns list and can be selected to appear in the WHERE clause of an UPDATE or DELETE statement.

**When to specify DateTimeAllowed**

You must specify a value for `DateTimeAllowed` *before* connecting to the database.

Applies to DIR Sybase DirectConnect  
IN9 Informix  
SYC Sybase Adaptive Server Enterprise

Syntax **DateTimeAllowed** = *value*

Parameter	Description
<i>value</i>	<p>Specifies whether you can use <code>DateTime</code> columns as unique key columns in a <code>WHERE</code> clause of a SQL <code>UPDATE</code> or <code>DELETE</code> statement generated by PowerBuilder to update the database. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Prohibit the use of <code>DateTime</code> columns in the <code>WHERE</code> clause of an <code>UPDATE</code> or <code>DELETE</code> statement. When <code>DateTimeAllowed</code> is set to 0, <code>DateTime</code> columns <i>do not display</i> in the Unique Key Columns list in the Specify Update Properties dialog box. You can also specify 'No' or 'False' to set this value.</li> <li>• <b>1</b> Allow the use of <code>DateTime</code> columns in the <code>WHERE</code> clause of an <code>UPDATE</code> or <code>DELETE</code> statement. When <code>DateTimeAllowed</code> is set to 1, <code>DateTime</code> columns <i>do display</i> in the Unique Key Columns list in the Specify Update Properties dialog box so you can select one or more to appear in the <code>WHERE</code> clause. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

Default value `DateTimeAllowed` = 0

Usage *When to set* To allow the use of `DateTime` columns as unique key columns in the `WHERE` clause of an `UPDATE` or `DELETE` statement when you are updating the database from a `DataWindow` object, set `DateTimeAllowed` to 1.

For instructions on using the Specify Update Properties dialog box to specify update characteristics for a `DataWindow` object, see the chapter on controlling updates in the *User's Guide*.

*What happens when you save the DataWindow object* When you set `DateTimeAllowed` to 1, select a `DateTime` column to appear in the `WHERE` clause, and then save the `DataWindow` object, this column continues to display in the Unique Key Columns list even if you set `DateTimeAllowed` to 0 on a subsequent connection.

**Examples** To allow the use of DateTime columns in the WHERE clause of an UPDATE or DELETE statement:

- **Database profile** Select the DateTime Datatype Allowed check box on the Syntax tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "DateTimeAllowed=1"
```

## DateTimeFormat

**Description** When you update data in the DataWindow painter, PowerBuilder builds a SQL UPDATE statement in the background. The DateTimeFormat parameter determines how PowerBuilder specifies a DateTime datatype when it builds the SQL UPDATE statement. (A DateTime datatype contains both a date value and a time value.)

**Applies to** ADO.NET  
OLE DB

**Syntax** `DateTimeFormat = 'datetime_format'`

Parameter	Description
<i>datetime_format</i>	The datetime format you want PowerBuilder to use when it builds a SQL UPDATE statement to update a data source in the DataWindow painter. For more on display formats, see the <i>User's Guide</i> .

**Default value** If no value is specified for the DateTimeFormat parameter, PowerBuilder does not use a datetime datatype.

**Usage** When you call stored procedures, the database server might not accept the DateTime format built by PowerBuilder. If this occurs, you can try to use another format. For example, for Microsoft SQL Server, try this format:

```
DateTimeFormat='\'yyyy-mm-dd hh:mm:ss.fff\''
```

**Examples** Assume you are updating a table named Files by setting the Timestamp column to 4/2/06 3:45 pm. This DateTime is represented by the following DateTime format:

```
m/d/yy h:mm am/pm
```

To specify that PowerBuilder should use this format for the DateTime datatype when it builds the SQL UPDATE statement:

- **Database profile** Type the following in the DateTime Format box on the Syntax tab in the Database Profile Setup dialog box:

```
m/d/yy h:mm am/pm
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "DateTimeFormat='m/d/yy h:mm am/pm'"
```

*What happens* PowerBuilder builds the following SQL UPDATE statement to update the table:

```
UPDATE FILES
SET TIMESTAMP = '4/2/06 3:45 pm'
```

See also

DateFormat  
TimeFormat

## DBConfigSection

Description

Specifies the section in a .NET configuration file to be used to specify custom configuration settings.

---

### When to specify DBConfigSection

You must specify a value for DBConfigSection *before* connecting to the database.

---

Applies to

ADO.NET

Syntax

**DBConfigSection** = 'value'

Parameter	Description
<i>value</i>	A string that specifies the section in a .NET configuration file to be used to specify DBParm values and the syntax used to obtain the value of an identity column. The value is the name of a section you create in a .NET configuration file.

Default value

None.

Usage

You can use the standard `select @@identity` syntax to obtain the value of an identity column. You can also use an alternative syntax, such as `select scope_identity()`, by adding sections to a .NET configuration file for your application.

The configuration file resides in the same directory as the application and has the same name as the application with the extension *.config*. It can contain multiple custom configuration sections. Each has two attributes: *dbParm* and *getIdentity*. You can set either or both of these attributes.

The *dbParm* value sets the value of the *DBParm* parameter of the transaction object. It has a maximum length of 1000 characters. If you set a value for a parameter in the configuration file, any value that you set in code or in the Database Profile Setup dialog box is overridden.

The *getIdentity* value specifies the syntax used to retrieve the value of an identity column. It has a maximum length of 100 characters. If you do not specify a value for *getIdentity*, the `select @@identity` syntax is used.

For more information about creating the configuration file, see the chapter on ADO.NET in *Connecting to Your Database*.

#### Examples

To specify that your PowerBuilder application uses the custom configuration file called *myconfig1*:

- **Database profile** Specify *myconfig1* in the ConfigSection Name in Configuration File box on the System tabpage in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="DBConfigSection='myconfig1'"
```

This sample configuration file for PowerBuilder 10.5 is called *pb105.exe.config*. It contains three custom configurations. The `<myconfig>` element sets both the *dbParm* and *getIdentity* attributes. `<myconfig1>` sets *getIdentity* only, and `<myconfig2>` sets *dbParm* only.

```
<configuration>
  <configSections>
    <sectionGroup name="dbConfiguration">
      <section name="myconfig"
        type="Sybase.PowerBuilder.Db.DbConfiguration,
        Sybase.PowerBuilder.Db, Version=10.5.0.9999,
        Culture=neutral,
        PublicKeyToken=9131e8bacdad8fb5"
      />
      <section name="myconfig1"
        type="Sybase.PowerBuilder.Db.DbConfiguration,
        Sybase.PowerBuilder.Db, Version=10.5.0.9999,
        Culture=neutral,
        PublicKeyToken=9131e8bacdad8fb5"
      />
    </sectionGroup>
  </configSections>

```



```

        <section name="myconfig2"
            type="Sybase.PowerBuilder.Db.DbConfiguration,
            Sybase.PowerBuilder.Db, Version=10.5.0.9999,
            Culture=neutral,
            PublicKeyToken=9131e8bacdad8fb5"
        />
    </sectionGroup>
</configSections>

<dbConfiguration>
    <myconfig dbParm="disablebind=0"
        getIdentity="select scope_identity()"
    />
    <myconfig1 getIdentity="select scope_identity()"
    />
    <myconfig2 dbParm=
        "Namespace='Oracle.DataAccess.Client',
        DataSource='ora10gen',DisableBind=0,
        NCharBind=1,ADORElease='10.1.0.301'"
    />
</dbConfiguration>
</configuration>

```

## DBGetTime

Description	<p>Specifies the number of seconds PowerBuilder waits for a response from the DBMS when you retrieve rows in a DataWindow object or query. When you set the Async parameter to 1 to enable asynchronous operation, you can also set the DBGetTime parameter for those DBMSs that support this parameter.</p> <p>If DBGetTime is set to 0 (the default), PowerBuilder waits indefinitely for a DBMS response (the request never times out). If the DBGetTime value expires before the first row is retrieved, your request is automatically canceled.</p>
Applies to	<p>DIR Sybase DirectConnect          IN9 Informix          JDB JDBC          ODBC (if driver and back-end DBMS support this feature)          O84 Oracle 8.x and Oracle8i (8.1.5 and higher database connections only)          O90 Oracle9i          O10 Oracle 10g          SYC Sybase Adaptive Server Enterprise</p>

Syntax

**DBGetTime** = *value*

Parameter	Description
<i>value</i>	The number of seconds PowerBuilder waits for a DBMS response while waiting to retrieve the first row of a DataWindow object, query, or report

Default value

DBGetTime = 0

Usage

*Requirements for using DBGetTime* To use the DBGetTime parameter, you must do *both* of the following:

- Set the Async parameter to 1 to enable asynchronous operation, as shown in the Examples.
- Code a RetrieveRow event for a DataWindow object or report.

Examples

To enable asynchronous operation and set the DBGetTime parameter to 20 seconds:

- **Database profile** Select the Asynchronous check box and type 20 in the Number Of Seconds To Wait box on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Async=1,DBGetTime=20"
```

See also

Async

## DBTextLimit

Description

Specifies the maximum length of a text field that DB-Library™ or CT-Library returns when you include the text field in a SQL SELECT statement.

You can set the DBTextLimit parameter if you want to include a long text string in a DataWindow object without treating the text as a binary large object (blob) datatype.

Applies to

DIR Sybase DirectConnect  
SYC and SYJ Sybase Adaptive Server Enterprise

Syntax	<p><b>DBTextLimit</b> = 'value'</p> <table border="1"> <thead> <tr> <th style="text-align: left;">Parameter</th> <th style="text-align: left;">Description</th> </tr> </thead> <tbody> <tr> <td><i>value</i></td> <td> <p>The maximum length in bytes of a text field that DB-Library or CT-Library returns when you include the text field in a SQL SELECT statement. The range of valid values is from 0 bytes to 32,763 bytes.</p> <p>When you set DBTextLimit to 0, DB-Library or CT-Library returns the maximum length text field.</p> </td> </tr> </tbody> </table>	Parameter	Description	<i>value</i>	<p>The maximum length in bytes of a text field that DB-Library or CT-Library returns when you include the text field in a SQL SELECT statement. The range of valid values is from 0 bytes to 32,763 bytes.</p> <p>When you set DBTextLimit to 0, DB-Library or CT-Library returns the maximum length text field.</p>
Parameter	Description				
<i>value</i>	<p>The maximum length in bytes of a text field that DB-Library or CT-Library returns when you include the text field in a SQL SELECT statement. The range of valid values is from 0 bytes to 32,763 bytes.</p> <p>When you set DBTextLimit to 0, DB-Library or CT-Library returns the maximum length text field.</p>				
Default value	The default value for DBTextLimit is the default specified by SQL Server for the DBTEXTLIMIT DB-Library or CS_TEXTLIMIT CT-Library connection property (see your SQL Server documentation).				
Usage	<p>The text field length that DB-Library or CT-Library returns is the lesser of the DBTextLimit value and the setting for the SQL Server global variable @@textsize.</p> <p>If the setting for @@textsize is less than the value you specify for DBTextLimit, DB-Library or CT-Library returns the @@textsize value.</p>				
Examples	<p>To have DB-Library or CT-Library return a text field that is up to 32,000 bytes long when you include the text field in a SQL SELECT statement:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Type 32000 in the Text Limit in SQL box (when using the SYC or SYJ interface), or Maximum Length of LongVarChar box (when using the DirectConnect interface) on the Syntax tab in the Database Profile Setup dialog box.</li> <li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm = "DBTextLimit='32000'"</pre> </li> </ul>				

## DecimalSeparator

Description	Specifies the decimal separator setting used by the back-end DBMS that you are accessing in PowerBuilder. If your DBMS uses a decimal separator other than period (.), which is the default, set DecimalSeparator to the value for your DBMS to ensure that PowerBuilder correctly handles numeric strings returned from your database.
Applies to	<p>ADO.NET</p> <p>DIR Sybase DirectConnect</p> <p>ODBC (if driver and back-end DBMS support this feature)</p> <p>OLE DB</p>

O84 Oracle 8.x and Oracle8i  
 O90 Oracle9i  
 O10 Oracle 10g

Syntax

**DecimalSeparator** = 'value'

Parameter	Description
value	<p>The decimal separator setting used by the back-end DBMS that you are accessing in PowerBuilder. Values are:</p> <ul style="list-style-type: none"> <li>'.' (Default) Specifies that your back-end DBMS uses a period (.) as the decimal separator. If you do not specify DecimalSeparator or if you specify a value other than period (.) or comma (,), PowerBuilder uses period (.) as the decimal separator.</li> <li>',' Specifies that your back-end DBMS uses a comma (,) as the decimal separator.</li> </ul>

Default value

DecimalSeparator = '.'

Usage

*When to set DecimalSeparator* The DecimalSeparator parameter currently supports period (.) and comma (,) as valid values. Therefore, if the decimal separator setting for your DBMS is a comma, you should set the DecimalSeparator parameter to ',' (comma) to make sure PowerBuilder correctly handles numeric strings returned from your database.

*Example using Oracle* Assume you are accessing an Oracle database in PowerBuilder and the decimal separator setting is a comma (,). Oracle returns to PowerBuilder the numeric string '123,50' containing a comma instead of a period as the decimal separator. PowerBuilder then sends this string to its decimal conversion routines.

By default, the PowerBuilder decimal conversion routines expect a period as the decimal separator. If you set the DecimalSeparator parameter to ',' (comma), PowerBuilder correctly handles this string and returns it as '123,50'.

Examples

To specify that your DBMS uses a comma (,) as the decimal separator setting:

- Database profile** Type a comma (,) in the Decimal Separator box on the Syntax tab in the Database Profile Setup dialog box.
- Application** Type the following in code:

```
SQLCA.DBParm = "DecimalSeparator=','"
```

See also

NumericFormat

## DefaultProcOwner

**Description** The DefaultProcOwner parameter lets you set a default owner for a stored procedure. The parameter takes effect only when the stored procedure is not qualified. For ODBC, the PBNewSPIInvocation parameter must also be set.

**Applies to** ADO.NET  
ODBC

**Syntax** **DefaultProcOwner**='value'

Parameter	Description
<i>value</i>	A string specifying the name of the default owner of the stored procedure

**Usage** The parameter can be set dynamically at runtime after connecting to a database. You can also set it in your *PBODB105.INI* file if you want to create and retrieve data into a DataWindow with a stored procedure data source in the DataWindow painter. The runtime setting overrides the setting in *PBODB105.INI*.

You can also cancel the setting at runtime. If you do so, PowerBuilder uses the current user as the owner of a non-qualified stored procedure when it obtains the parameters of the stored procedure.

**Examples** To set the default owner to `proms` in *PBODB105.INI*:

```
[Adaptive Server Anywhere]
DefaultProcOwner='proms'
```

In code:

```
SQLCA.DBParm="DefaultProcOwner='proms'";
```

To cancel the setting:

```
SQLCA.DBParm="DefaultProcOwner=' '";
```

Note that the single quotes in the previous example contain an empty string, not a space.

**See also** PBNewSPIInvocation

## DelimitIdentifier

**Description** Specifies whether you want PowerBuilder to enclose the names of tables, columns, indexes, and constraints in double quotes when it generates SQL statements. This affects the behavior of any PowerBuilder painter that generates SQL syntax.

**Applies to** ADO.NET  
 DIR Sybase DirectConnect  
 Informix 9  
 JDB JDBC  
 ODBC (if driver and back-end DBMS support this feature)  
 OLE DB  
 O84 Oracle 8.x and Oracle8i  
 O90 Oracle9i  
 O10 Oracle 10g  
 SYC Sybase Adaptive Server Enterprise

**Syntax** **DelimitIdentifier** = 'value'

Parameter	Description
value	Specifies whether you want PowerBuilder to enclose table and column names in double quotes. Values are: <ul style="list-style-type: none"> <li>• <b>Yes</b> Use double quotes</li> <li>• <b>No</b> Do not use double quotes</li> </ul>

**Default value** The default value for the DelimitIdentifier parameter depends on the DBMS you are accessing, as follows:

DBMS	DelimitIdentifier default value
ADO.NET	DelimitIdentifier = 'No'
Informix	DelimitIdentifier = 'No'
JDBC	Depends on the DelimitIdentifier setting in the registry
ODBC	Depends on the DelimitIdentifier setting in the PBODB105 initialization file
Oracle	DelimitIdentifier = 'Yes'
OLE DB	DelimitIdentifier = 'Yes'
Sybase DirectConnect	DelimitIdentifier = 'No'
Sybase Adaptive Server Enterprise	DelimitIdentifier = 'No'

## Usage

*Informix* Informix database servers can create a log of database transactions in either ASCII or non-ASCII format. If the database is creating a non-ASCII log, the setting of the DelimitIdentifier is optional. If the database is creating an ASCII log, you must set DelimitIdentifier = 'Yes' to make the SQL syntax generated by PowerBuilder behave as expected.

*Sybase Adaptive Server Enterprise* When you set DelimitIdentifier to 'Yes', the “set quoted\_identifier on” command is automatically sent to Adaptive Server to adjust your database connection on the server. Otherwise, the “set quoted\_identifier off” command is sent to the server. This feature occurs with SYC, JDBC, ODBC, and OLE DB interfaces.

*Microsoft SQL Server* When you set DelimitIdentifier to 'Yes', the “set quoted\_identifier on” command is automatically sent to Microsoft SQL Server to adjust your database connection on the server when you use OLE DB. Otherwise, the “set quoted\_identifier off” command is sent to the server.

*JDBC and ODBC* The DelimitIdentifier parameter setting overrides the DelimitIdentifier setting specified for your JDBC driver in the registry and for your ODBC driver in the PBODB105 initialization file.

*DirectConnect* If you want to use mixed-case identifier names, you must set DelimitIdentifier = 'Yes'. Also, you must set LowerCaseIdent = 'No' to preserve case sensitivity of identifiers stored in the DB2 system catalog.

## Examples

To specify that PowerBuilder should not enclose table and column names in double quotes when it generates SQL statements:

- **Database profile** Clear the Enclose Table And Column Names In Quotes check box on the Syntax tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Delimitidentifier='No'"
```

## See also

LowerCaseIdent

## DisableBind

### Description

For those DBMSs that support bind variables, PowerBuilder binds input parameters to a compiled SQL statement by default. The DisableBind parameter allows you to specify whether you want to disable this default binding.

When you set DisableBind to 1 to disable the binding, PowerBuilder replaces the input variable with the value entered by the application user or specified in code.

### Applies to

ADO.NET  
Informix 9  
JDB JDBC  
ODBC (if driver and back-end DBMS support this feature)  
OLE DB  
O84 Oracle 8.x and Oracle8i  
O90 Oracle9i  
O10 Oracle 10g

### Syntax

**DisableBind** = *value*

Parameter	Description
<i>value</i>	Specifies whether you want to disable the default binding of input parameters to a compiled SQL statement. Values are: <ul style="list-style-type: none"><li>• <b>0</b> PowerBuilder binds input parameters to a compiled SQL statement.</li><li>• <b>1</b> PowerBuilder does <i>not</i> bind input parameters to a compiled SQL statement.</li></ul>

### Default value

DisableBind = 1 for ADO.NET and OLE DB, DisableBind=0 for other interfaces

### Usage

*Bind variables* In a SQL statement, a **bind variable** is a placeholder for a column value. By default, PowerBuilder associates (binds) data from a variable defined in your application to the bind variable each time the SQL statement executes.

*Using bind variables in SQL statements* For example, the following SQL statement retrieves those rows in the Books table about books written by Hemingway:

```
SELECT * FROM books WHERE author = "Hemingway"
```



Suppose that you want to execute this statement to get information about books written by other authors. Instead of compiling and executing a new statement for each author, you can define a bind variable that represents the author's name. The user then supplies the author's actual name when the application executes. By using bind variables, you ensure that the statement is compiled only once and executed repeatedly with new values supplied by the user.

If your database supports bind variables and `DisableBind` is set to 0 to enable binding (the default for all database interfaces except ADO.NET and OLE DB), PowerBuilder generates the statement with parameter markers (`:bind_param`) and passes the actual parameter value at execution time. For example:

```
SELECT * FROM books WHERE author = :bind_param
```

---

### Using the DataDirect ODBC driver

The DataDirect wire protocol driver for Sybase Adaptive Server Enterprise does not support the SQL describe parameter function that is necessary to support the `DisableBind=0` feature. If you use this driver, setting `DisableBind=0` has no effect.

---

*Bind variables and cached statements* Using bind variables in conjunction with cached statements can improve the performance of most applications, depending on the application. In general, applications that perform a large amount of transaction processing benefit the most from using bind variables and cached statements.

In order to use cached statements, make sure that `DisableBind` is set to 0. This enables the binding of input variables to SQL statements in PowerBuilder. (For more about using cached statements, see the description of the `SQLCache` parameter.)

*Performance improvements* For Adaptive Server Anywhere and Oracle databases, bind variables improve performance by allowing PowerBuilder to insert and modify strings that exceed 255 characters.

*Bind variables and default column values* When `DisableBind` is set to 0 to enable the use of bind variables, the DataWindow painter does both of the following to get maximum performance improvement from using bind variables when you add rows to a DataWindow object:

- Generates a SQL INSERT statement that includes all columns (except identity and SQL Server timestamp)
- Reuses this SQL INSERT statement for each row you add to the DataWindow object

For example, if a table named Order\_T contains three columns named Order\_ID, Order\_Date, and Customer\_ID, the DataWindow painter generates the following SQL INSERT statement when DisableBind is set to 0 (default binding enabled):

```
INSERT INTO Order_T(Order_ID, Order_Date, Customer_ID)
VALUES (:bind_param1, :bind_param2, :bind_param3)
```

If one of these columns is null, the DataWindow painter sets a null value indicator for this column parameter and executes the statement. This behavior is important to understand if you want your back-end DBMS to set a default value for any columns in your DataWindow object.

To illustrate, suppose that your application users do not enter a value for the Order\_Date column because they expect the back-end DBMS to set this column to a default value of TODAY. Then, they retrieve the row and find that a null value has been set for Order\_Date instead of its default value. This happens because the SQL INSERT statement generated by the DataWindow painter specified a null value indicator, so the DBMS set the column value to null instead of to its default value as expected.

*Setting a default column value when binding is enabled* If you are using bind variables (DisableBind set to 0) and want the back-end DBMS to set a column to its default value when your application user does not explicitly enter a value in a new row, you should set an initial value for the DataWindow object column that mirrors the DBMS default value for this column.

In the DataWindow painter, you can set or modify a column's initial value in the Column Specifications dialog box.

For more about the Column Specifications dialog box, see the *User's Guide*.

*Setting a default column value when binding is disabled* If you are *not* using bind variables (DisableBind set to 1) and want the back-end DBMS to set a column to its default value when your application user does not explicitly enter a value in a new row, you do *not* need to set an initial value for the DataWindow column.

This is because with bind variables disabled, the DataWindow painter generates a SQL INSERT statement for each row added to the DataWindow object. If a column does not contain an explicit value, it is not included in the SQL INSERT statement.

Using the Order\_T table example, if your application user enters 123 as the value for the Order\_ID column and A-123 as the value for the Customer\_ID column, the DataWindow painter generates the following SQL INSERT statement when DisableBind is set to 1 (binding disabled):

```
INSERT INTO Order_T(Order_ID, Customer_ID)
VALUES(123, 'A-123')
```

Your back-end DBMS would then set the Order\_Date column to its default value as expected, since a value for Order\_Date is not explicitly set in the SQL INSERT statement generated by the DataWindow painter.

#### Examples

To specify that PowerBuilder should disable the binding of input parameters to a compiled SQL statement:

- **Database profile** Select the Disable Bind check box on the Transaction or System tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "DisableBind=1"
```

#### See also

SQLCache

## DisableUnicode

#### Description

Specifies whether data is retrieved from the database as ANSI or Unicode. Use this parameter if the client is configured to use a character set that does not allow characters such as the Euro symbol to be converted correctly.

#### Applies to

O84 Oracle 8.x and Oracle8i

#### Syntax

**DisableUnicode** = *value*

Parameter	Description
<i>value</i>	Specifies whether data is retrieved from the database as ANSI or Unicode. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> PowerBuilder retrieves data as Unicode.</li> <li>• <b>1</b> PowerBuilder retrieves data as ANSI.</li> </ul>

#### Default value

DisableUnicode =0

#### Usage

When the client is configured to use a character set such as WE8ISO8859P15, some special characters, including the Euro symbol, are not converted correctly when retrieved from an Oracle8i database. The O84 driver retrieves Unicode characters from the database by default, and the Euro symbol is not recognized as a valid Unicode character in this character set.

You can set the `DisableUnicode` database parameter to retrieve ANSI characters from the database instead of Unicode characters. The retrieved ANSI characters are then converted to a Unicode string.

**Examples**

To specify that PowerBuilder should retrieve ANSI characters from the database:

- **Database profile** Select the `Disable Unicode Support` check box on the `Connection` page in the `Database Profile Setup` dialog box for `Oracle8i`.
- **Application** Type the following in code:

```
SQLCA.DBParm = "DisableUnicode=1"
```

## Driver

**Description**

The JDBC driver your application uses to connect to the database.

---

**When to specify Driver**

You must specify the `Driver` database parameter *before* connecting to the database.

---

**Applies to**

JDB JDBC

**Syntax**

```
Driver = 'driver_name'
```

**Default value**

None

**Usage**

The driver name identifies the Java class name for the particular driver you are using to connect to the database.

**Examples**

**Example 1** To set the driver name of a Sybase jConnect driver:

- **Database profile** Type the following in the `Driver Name` box on the `Connection` tab in the `Database Profile Setup` dialog box:

```
com.sybase.jdbc.SybDriver
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "Driver =  
'com.sybase.jdbc.SybDriver' "
```

**Example 2** To set the driver name of an Oracle JDBC Driver:

- **Database profile.** Type the following in the `Driver Name` box on the `Connection` tab in the `Database Profile Setup` dialog box.

```
oracle.jdbc.driver.OracleDriver
```

- **Application.** Type the following in code:

```
SQLCA.DBParm = "Driver =
'oracle.jdbc.driver.OracleDriver' "
```

See also

URL

## DS\_Alias

Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, DS\_Alias is one of several parameters that you can set to enable network-based directory services in your application. (For other directory services parameters, see the See Also section.)

Some directory service providers and drivers support the creation of alias entries. An **alias entry** provides a link to a primary directory entry in a hierarchy, thereby giving users multiple ways to access the primary entry while searching the directory structure for a particular network entity.

For those directory service providers and drivers that support aliases, DS\_Alias specifies whether the provider is allowed to follow links for (expand) alias entries while searching the directory hierarchy. The default behavior is to allow expansion of alias entries for providers that support this feature.

You must specify a value for DS\_Alias *before* connecting to the database in PowerBuilder.

---

### Using third-party directory service providers

For information about the third-party directory service providers and operating system platforms that Sybase has tested with Open Client directory services, see the Open Client documentation.

---

Applies to

SYC Sybase Adaptive Server Enterprise

Syntax

**DS\_Alias** = *value*

Parameter	Description
<i>value</i>	<p>For those directory services providers and drivers that support aliases, specifies whether the provider is allowed to expand alias entries while searching a directory hierarchy. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> Prohibit provider from expanding alias entries during a directory search. You can also specify 'No' or 'False' to set this value.</li> <li>• <b>1</b> (Default) Allow provider to expand alias entries during a directory search. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

Default value	DS_Alias = 1
Usage	<p><i>When to use</i> To prevent access to your data through directory alias entries, set DS_Alias to 0. This prohibits directory service providers that support aliases from expanding alias entries during a directory search.</p> <p><i>Set Release parameter</i> For this parameter to take effect, you <i>must</i> also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.</p> <p><i>Requirements for use</i> To use DS_Alias or any other parameter supporting Open Client directory services, you must meet certain requirements for using directory services in your PowerBuilder application. For details, see “Requirements for using Open Client directory services” in <i>Connecting to Your Database</i>.</p> <p><i>Corresponding CT-Lib connection property</i> Specifying a value for DS_Alias sets the corresponding Sybase CT-Lib connection property named CS_DS_EXPANDALIAS.</p>
Examples	<p>To prohibit directory service providers that support aliases from expanding alias entries during a directory search:</p> <ul style="list-style-type: none"><li>• <b>Database profile</b> Clear the Directory Alias Entries check box on the Directory Services tab in the Database Profile Setup dialog box.</li><li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm = "DS_Alias=0"</pre></li></ul>
See also	<p>DS_Copy DS_DitBase DS_Failover DS_Password DS_Principal DS_Provider DS_TimeLimit Release</p>

## DS\_Copy

### Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, DS\_Copy is one of several parameters that you can set to enable network-based directory services in your application. (For other directory services parameters, see the See Also section.)

Some directory service providers and drivers support the use of caching. **Caching** allows a directory service provider to use cached information while searching a directory instead of making a request to the directory server agent for information.

For those directory service providers and drives that support caching, DS\_Copy specifies whether the provider is allowed to use cached information during a directory search. The default behavior is to allow providers that support this feature to use cached information.

You must specify a value for DS\_Copy *before* connecting to the database in PowerBuilder.

---

### Using third-party directory service providers

For information about the third-party directory service providers and operating system platforms that Sybase has tested with Open Client directory services, see the Open Client documentation.

---

### Applies to

SYC Sybase Adaptive Server Enterprise

### Syntax

**DS\_Copy** = *value*

Parameter	Description
<i>value</i>	<p>For those directory services providers and drivers that support caching, specifies whether the provider is allowed to use cached information when making a directory search. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> Prohibit provider from using cached information during a directory search. You can also specify 'No' or 'False' to set this value.</li> <li>• <b>1</b> (Default) Allow provider to use cached information when making a directory search. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

### Default value

DS\_Copy = 1

### Usage

*When to use* Allowing providers to use cached information during directory searches makes the searches faster, but does not ensure that the provider is using the most up-to-date directory information.

To ensure that the application gets the most recent changes to directory entries when it requests directory information, set DS\_Copy to 0 to prohibit providers that support caching from using cached information during a directory search.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use DS\_Copy or any other parameter supporting Open Client directory services, you must meet certain requirements for using directory services in your PowerBuilder application. For details, see “Requirements for using Open Client directory services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for DS\_Copy sets the corresponding Sybase CT-Lib connection property named CS\_DS\_COPY.

Examples

To prohibit directory service providers that support caching from using cached information during a directory search:

- **Database profile** Clear the Use Caching check box on the Directory Services tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "DS_Copy=0"
```

See also

DS\_Alias  
DS\_DitBase  
DS\_Failover  
DS\_Password  
DS\_Principal  
DS\_Provider  
DS\_TimeLimit  
Release



## DS\_DitBase

### Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, DS\_DitBase is one of several parameters that you can set to enable network-based directory services in your application. (For other directory services parameters, see the See Also section.)

When you use Open Client directory services, a default (active) directory information tree base (DIT base) is specified in the Open Client/Server™ Configuration utility. The **DIT base** is the directory node where directory searches start. This is analogous to the current working directory in MS-DOS file systems.

DS\_DitBase lets you specify the name of the directory node where you want searches for directory entries to start. The DS\_DitBase value you specify must be a fully qualified name that uses the syntax required by your directory service provider and driver (see the Examples section for illustrations).

The default value for DS\_DitBase is the DIT base currently specified as active in the Open Client/Open Server Configuration utility.

You must specify a value for DS\_DitBase *before* connecting to the database in PowerBuilder.

---

### Using third-party directory service providers

For information about the third-party directory service providers and operating system platforms that Sybase has tested with Open Client directory services, see the Open Client documentation.

---

### Applies to

SYC Sybase Adaptive Server Enterprise

### Syntax

**DS\_DitBase** = '*dit\_base*'

Parameter	Description
<i>dit_base</i>	<p>The name of the directory node where you want directory searches to start. By default, this is the DIT base currently specified as active in the Open Client/Open Server Configuration utility.</p> <p>The value for <i>dit_base</i> must be a fully qualified name that uses the syntax required by your directory service provider and driver. The syntax for specifying the DIT base varies for different providers; see your provider's documentation for details.</p> <p>For examples of how to specify <i>dit_base</i> for different directory service providers, see the Examples section.</p>

**Default value** The default value for DS\_DitBase is the DIT base currently specified as active in the Open Client/Open Server Configuration utility.

**Usage** *When to use* Set DS\_DitBase to specify a starting node for directory searches *other than* the DIT base node specified as active in the Open Client/Open Server Configuration utility. For instructions on using the Open Client/Open Server Configuration utility, see your Sybase Open Client/Server configuration guide.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use DS\_DitBase or any other parameter supporting Open Client directory services, you must meet certain requirements for using directory services in your PowerBuilder application. For details, see “Requirements for using Open Client directory services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for DS\_DitBase sets the corresponding Sybase CT-Lib connection property named CS\_DS\_DITBASE.

**Examples** **About these examples** The examples that follow show how to specify a DS\_DitBase value for different directory service providers.

See your directory service provider’s documentation for complete information about the format your provider requires for specifying the DIT base.

**Example 1 (Windows NT Registry)** This example shows the syntax for DS\_DitBase if your directory service provider is the Windows NT Registry:

```
Node name: SALES:software\sybase\server\SYS11NT
DS_DitBase: SALES:software\sybase\server
```

To set DS\_DitBase:

- **Database profile** Type the following in the DIT Base box on the Directory Services tab in the Database Profile Setup dialog box. Do *not* end the DS\_DitBase value with a backslash (\):

```
SALES:software\sybase\server
```

- **Application** Type the following in code. Do *not* end the DS\_DitBase value with a backslash (\):

```
SQLCA.DBParm =
    "DS_DitBase='SALES:software\sybase\server' "
```

**Example 2 (DCE/CDS)** This example shows the syntax for DS\_DitBase if your directory service provider is Distributed Computing Environment Cell Directory Services (DCE/CDS):

```
Node name: /.../boston.sales/dataservers/sybase/SYS11
DS_DitBase: /.../boston.sales/dataservers
```

To set DS\_DitBase:

- **Database profile** Type the following in the DIT Base box on the Directory Services tab in the Database Profile Setup dialog box. Do *not* end the DS\_DitBase value with a slash (/):

```
/.../boston.sales/dataservers
```

- **Application** Type the following in code. Do *not* end the DS\_DitBase value with a slash (/):

```
SQLCA.DBParm = "DS_DitBase =
'/.../boston.sales/dataservers' "
```

**Example 3 (Banyan STDA)** This example shows the syntax for DS\_DitBase if your directory service provider is Banyan StreetTalk Directory Assistance (STDA):

```
Node name: SYS11@sales@chicago
DS_DitBase: chicago
```

To set DS\_DitBase:

- **Database profile** Type the following in the DIT Base box on the Directory Services tab in the Database Profile Setup dialog box. Do *not* start the DS\_DitBase value with @:

```
chicago
```

- **Application** Type the following. Do *not* start the DS\_DitBase value with @:

```
SQLCA.DBParm = "DS_DitBase = 'chicago' "
```

**Example 4 (Novell NDS)** This example shows the syntax for DS\_DitBase if your directory service provider is Novell NetWare Directory Services (NDS):

```
Node name: CN=SYS11.OU=miami.OU=sales.O=sybase
DS_DitBase: OU=miami.OU=sales.O=sybase
```

To set DS\_DitBase:

- **Database profile** Type the following in the DIT Base box on the Directory Services tab in the Database Profile Setup dialog box:

```
OU=miami.OU=sales.O=sybase
```

- **Application** To specify DS\_DitBase in code, type the following:

```
SQLCA.DBParm = "DS_DitBase =  
'OU=miami.OU=sales.O=sybase' "
```

See also

DS\_Alias  
DS\_Copy  
DS\_Failover  
DS\_Password  
DS\_Principal  
DS\_Provider  
DS\_TimeLimit  
Release

## DS\_Failover

Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, DS\_Failover is one of several parameters that you can set to enable network-based directory services in your application. (For other directory services parameters, see the See Also section.)

Sybase Open Client Client-Library (CT-Lib) requires a directory to map logical server names to network addresses. The source for this directory can be either the Sybase Interfaces file or a network-based directory service provider (such as DCE Cell Directory Services or the Windows Registry).

If you want an application to use a directory source *other than* the Interfaces file, CT-Lib must be able to load the appropriate directory driver. If CT-Lib cannot load the required driver, you can set DS\_Failover to specify whether CT-Lib should silently default (fail over) to using the Interfaces file as the directory source.

By default, DS\_Failover specifies that CT-Lib should use the Interfaces file as the directory source if it cannot load the requested directory driver.

You must specify a value for DS\_Failover *before* connecting to the database in PowerBuilder.

---

### Using third-party directory service providers

For information about the third-party directory service providers and operating system platforms that Sybase has tested with Open Client directory services, see the Open Client documentation.

---

Applies to

SYC Sybase Adaptive Server Enterprise

## Syntax

**DS\_Failover** = *value*

Parameter	Description
<i>value</i>	<p>Specifies whether Sybase CT-Lib should silently default (fail over) to using the Interfaces file as the directory source if it cannot load the requested directory driver. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> Prohibit CT-Lib from using the Interfaces file as the directory source if it cannot load the requested directory driver. You can also specify 'No' or 'False' to set this value.</li> <li>• <b>1</b> (Default) Allow CT-Lib to use the Interfaces file as the directory source if it cannot load the requested directory driver. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

## Default value

DS\_Failover = 1

## Usage

*When to use* To prevent CT-Lib from using the Interfaces file as the directory source if it cannot load the requested directory driver, set DS\_Failover to 0.

If DS\_Failover is set to 0 to prevent use of the Interfaces file and CT-Lib cannot load the requested directory driver, the connection's directory source is undefined. This causes certain operations requiring directory access to fail.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use DS\_Failover or any other parameter supporting Open Client directory services, you must meet certain requirements for using directory services in your PowerBuilder application. For details, see “Requirements for using Open Client directory services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for DS\_Failover sets the corresponding Sybase CT-Lib connection property named CS\_DS\_FAILOVER.

## Examples

To prohibit CT-Lib from using the Interfaces file as the directory source if it cannot load the requested directory driver:

- **Database profile** Clear the Enable Failover check box on the Directory Services tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "DS_Failover = 0"
```

See also DS\_Alias  
 DS\_Copy  
 DS\_DitBase  
 DS\_Password  
 DS\_Principal  
 DS\_Provider  
 DS\_TimeLimit  
 Release

## DS\_Password

**Description** When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client 12.5 or higher software, DS\_Password is one of several parameters that you can set to enable network-based directory services in your application. (For other directory services parameters, see the See Also section.)

Some directory service providers and drivers require an authenticated principal (user ID) name and password to control an application's access to directory entries. For those providers and drivers, DS\_Principal and DS\_Password specify the principal name and password your application should use to identify you to the directory service provider.

You must specify a value for DS\_Password *before* connecting to the database in PowerBuilder.

**Applies to** SYC Sybase Adaptive Server Enterprise

**Syntax** **DS\_Password** = '*password*'

Parameter	Description
<i>password</i>	The password associated with the principal (user ID) name you specified in the DS_Principal parameter.

**Default value** None

PowerBuilder does not set DS\_Password or the corresponding Sybase Open Client Client-Library (CT-Lib) connection parameter CS\_DS\_PASSWORD if you do not specify a value.

**Usage** *When to use* If your directory service provider requires an authenticated principal name for directory access, set DS\_Password to the password that goes with your directory service principal name.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use DS\_Password or any other parameter supporting Open Client 12.5 directory services, you must meet certain requirements for using directory services in your PowerBuilder application. For details, see “Requirements for using Open Client directory services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for DS\_Password sets the corresponding Sybase CT-Lib connection property named CS\_DS\_PASSWORD.

#### Examples

To specify MYPASS as your application's password:

- **Database profile** Type the following in the Password box on the Directory Services tab in the Database Profile Setup dialog box:

```
MYPASS
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "DS_Password='MYPASS' "
```

#### See also

DS\_Alias  
DS\_Copy  
DS\_DitBase  
DS\_Failover  
DS\_Principal  
DS\_Provider  
DS\_TimeLimit  
Release

## DS\_Principal

### Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, DS\_Principal is one of several parameters that you can set to enable network-based directory services in your application. (For other directory services parameters, see the See Also section.)

Some directory service providers and drivers require an authenticated principal (user ID) name to control an application's access to directory entries. For those providers and drivers, DS\_Principal and DS\_Password specify the principal name and password your application should use to identify you to the directory service provider.

You must specify a value for DS\_Principal *before* connecting to the database in PowerBuilder.

---

### Using third-party directory service providers

For information about the third-party directory service providers and operating system platforms that Sybase has tested with Open Client directory services, see the Open Client documentation.

---

### Applies to

SYC Sybase Adaptive Server Enterprise

### Syntax

**DS\_Principal** = '*principal\_name*'

Parameter	Description
<i>principal_name</i>	The principal (user ID) name your application should use to identify you to the directory service provider.

### Default value

None

PowerBuilder does not set DS\_Principal or the corresponding Sybase Open Client Client-Library (CT-Lib) connection parameter CS\_DS\_PRINCIPAL if you do not specify a value.

### Usage

*When to use* If your directory service provider requires an authenticated principal name for directory access, set DS\_Principal to the principal (user ID) name that goes with your directory service password.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.



*Requirements for use* To use DS\_Principal or any other parameter supporting Open Client directory services, you must meet certain requirements for using directory services in your PowerBuilder application. For details, see “Requirements for using Open Client directory services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for DS\_Principal sets the corresponding Sybase CT-Lib connection property named CS\_DS\_PRINCIPAL.

#### Examples

To specify JSMITH as your application's principal name:

- **Database profile** Type the following in the Principal Name box on the Directory Services tab in the Database Profile Setup dialog box:

```
JSMITH
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "DS_Principal = 'JSMITH' "
```

#### See also

DS\_Alias  
DS\_Copy  
DS\_DitBase  
DS\_Failover  
DS\_Password  
DS\_Provider  
DS\_TimeLimit  
Release

## DS\_Provider

#### Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, DS\_Provider is one of several parameters that you can set to enable network-based directory services in your application. (For other directory services parameters, see the See Also section.)

When you use Open Client directory services, you must specify your directory service provider names in the Open Client/Open Server Configuration utility so that the required drivers can be loaded for each provider. The default directory service provider is the one currently specified as active in the Configuration utility.

DS\_Provider lets you specify a directory service provider name listed in the Open Client/Open Server Configuration utility *other than* the default (active) provider. The default value for DS\_Provider is the provider name currently specified as active in the Configuration utility.

You must specify a value for DS\_Provider *before* connecting to the database in PowerBuilder.

---

**Using third-party directory service providers**

For information about the third-party directory service providers and operating system platforms that Sybase has tested with Open Client directory services, see the Open Client documentation.

---

Applies to

SYC Sybase Adaptive Server Enterprise

Syntax

**DS\_Provider** = 'provider\_name'

Parameter	Description
<i>provider_name</i>	The directory service provider name you want to use for directory services.  The provider name is case sensitive. You must specify it <i>exactly as it appears</i> in the Open Client/Open Server Configuration utility.

Default value

The default value for DS\_Provider is the provider name currently specified as active in the Open Client/Open Server Configuration utility.

Usage

*When to use* Set DS\_Provider to use a directory service provider specified in the Open Client/Open Server Configuration utility *other than* the default (active) provider. For instructions on using the Open Client/Open Server Configuration utility, see your Sybase Open Client/Server configuration guide.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use DS\_Provider or any other parameter supporting Open Client directory services, you must meet certain requirements for using directory services in your PowerBuilder application. For details, see “Requirements for using Open Client directory services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for DS\_Provider sets the corresponding Sybase CT-Lib connection property named CS\_DS\_PROVIDER.

Examples	<p>To specify NTREGISTRY as the directory service provider name:</p> <ul style="list-style-type: none"> <li>• <b>Database profile.</b> Type the following in the Provider box on the Directory Services tab in the Database Profile Setup dialog box: <pre>NTREGISTRY</pre> </li> <li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm = "DS_Provider='NTREGISTRY'"</pre> </li> </ul>
See also	<p>DS_Alias  DS_Copy  DS_DitBase  DS_Failover  DS_Password  DS_Principal  DS_TimeLimit  Release</p>

## DS\_TimeLimit

Description	<p>When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, DS_TimeLimit is one of several parameters that you can set to enable network-based directory services in your application. (For other directory services parameters, see the See Also section.)</p> <p>Some directory service providers and drivers support the use of time limits for a directory search. For those providers and drivers, DS_TimeLimit specifies the maximum number of seconds that a directory search lasts.</p> <p>By default, DS_TimeLimit specifies that there is no time limit for a directory search.</p> <p>You must specify a value for DS_TimeLimit <i>before</i> connecting to the database in PowerBuilder.</p> <hr/> <p><b>Using third-party directory service providers</b>  For information about the third-party directory service providers and operating system platforms that Sybase has tested with Open Client directory services, see the Open Client documentation.</p> <hr/>
Applies to	SYC Sybase Adaptive Server Enterprise

## Syntax

**DS\_TimeLimit**='value'

Parameter	Description
<i>value</i>	Specifies the maximum number of seconds that you want a directory search to last. You can also specify 'no_limit' (the default) to indicate that there is no time limit for the directory search.  If the specified time limit expires and the target has not been found, the directory search is unsuccessful and the PowerBuilder connection fails.

## Default value

DS\_TimeLimit = 'no\_limit'

## Usage

*Set Release parameter* For DS\_TimeLimit to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use DS\_TimeLimit or any other parameter supporting Open Client directory services, you must meet certain requirements for using directory services in your PowerBuilder application. For details, see “Requirements for using Open Client directory services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for DS\_TimeLimit sets the corresponding Sybase CT-Lib connection property named CS\_DS\_TIMELIMIT.

## Examples

To specify that you want the directory search to last a maximum of 120 seconds (2 minutes):

- **Database profile** Type 120 in the Directory Search Time Limit box on the Directory Services tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="DS_TimeLimit = 120"
```

## See also

DS\_Alias  
DS\_Copy  
DS\_DitBase  
DS\_Failover  
DS\_Password  
DS\_Principal  
DS\_Provider  
Release

## EncryptPassword

**Description** Specifies whether you want PowerBuilder to encrypt your password automatically when connecting to an OLE DB data provider.

---

### When to specify EncryptPassword

You must specify the EncryptPassword parameter *before* connecting to the database.

---

**Applies to** OLE DB

**Syntax** `EncryptPassword = 'value'`

Parameter	Description
<i>value</i>	Specifies whether you want PowerBuilder to encrypt your password. Values are: <ul style="list-style-type: none"> <li>• <b>True</b> Tells PowerBuilder to encrypt the password</li> <li>• <b>False</b> (Default) Tells PowerBuilder not to encrypt the password</li> </ul>

**Default value** `EncryptPassword = 'False'`

**Examples** To tell PowerBuilder to encrypt your password when connecting to an OLE DB data provider:

- **Database profile** Select the Encrypt Password check box on the Security tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="EncryptPassword=' True ' "
```

**See also** DataLink  
IntegratedSecurity  
MaskPassword  
PersistEncrypted

## FoDelay

**Description** Specifies the amount of time (in milliseconds) you want PowerBuilder to wait between attempts to fail over to another database server if the current database server goes down.

---

**When to specify FoDelay**

You must specify the FoDelay parameter *before* connecting to the database.

---

**Applies to** O84 Oracle 8.x and Oracle8i (8.1.5 and higher database connections only)  
O90 Oracle9i  
O10 Oracle 10g

**Syntax** **FoDelay='value'**

Parameter	Description
<i>value</i>	Specifies the amount of time in milliseconds you want PowerBuilder to wait between attempts to fail over to an another database server.

**Default value** FoDelay = '10'

**Usage** You can enter a failover delay value only if you have enabled failover.

This parameter cannot be set dynamically. The value set when the connection is made remains in effect until it is disconnected.

**Examples** To tell PowerBuilder to wait 20 milliseconds between attempts to fail over:

- **Database profile** Type 20 in the Delay box on the Network tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="FoDelay='20' "
```

**See also** SvrFailover

## FoDialog

**Description** Specifies whether PowerBuilder displays a runtime dialog box indicating when a failover occurs.

---

**When to specify FoDialog**

You must specify the FoDialog parameter *before* connecting to the database.

---

Applies to	O84 Oracle 8.x and Oracle8i (8.1.5 and higher database connections only) O90 Oracle9i O10 Oracle 10g SYC				
Syntax	<b>FoDialog</b> ='value'				
	<table border="1"> <thead> <tr> <th>Parameter</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><i>value</i></td> <td>Specifies whether you want PowerBuilder to display a runtime dialog box indicating when a failover occurs. Values are: <ul style="list-style-type: none"> <li>• <b>No</b> (Default) PowerBuilder should not display a dialog box.</li> <li>• <b>Yes</b> PowerBuilder should display a dialog box.</li> </ul> </td> </tr> </tbody> </table>	Parameter	Description	<i>value</i>	Specifies whether you want PowerBuilder to display a runtime dialog box indicating when a failover occurs. Values are: <ul style="list-style-type: none"> <li>• <b>No</b> (Default) PowerBuilder should not display a dialog box.</li> <li>• <b>Yes</b> PowerBuilder should display a dialog box.</li> </ul>
Parameter	Description				
<i>value</i>	Specifies whether you want PowerBuilder to display a runtime dialog box indicating when a failover occurs. Values are: <ul style="list-style-type: none"> <li>• <b>No</b> (Default) PowerBuilder should not display a dialog box.</li> <li>• <b>Yes</b> PowerBuilder should display a dialog box.</li> </ul>				
Default value	FoDialog = 'No'				
Usage	You can display a runtime dialog box only if you have enabled failover. The dialog box does not display in EAServer or COM+.  This parameter cannot be set dynamically. The value set when the connection is made remains in effect until it is disconnected.				
Examples	To tell PowerBuilder to display a runtime dialog box when a failover occurs: <ul style="list-style-type: none"> <li>• <b>Database profile</b> Select the Display Runtime Dialog When Failing Over check box on the Network tab in the Database Profile Setup dialog box.</li> <li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm = "FoDialog = 'Yes'"</pre> </li> </ul>				
See also	SvrFailover				

## FoRetryCount

**Description** Specifies the number of times you want PowerBuilder to try to fail over to another database server if the current database server goes down.

---

### When to specify FoRetryCount

You must specify the FoRetryCount parameter *before* connecting to the database.

---

**Applies to** O84 Oracle 8.x and Oracle8i (8.1.5 and higher database connections only)  
O90 Oracle9i  
O10 Oracle 10g

Syntax	<b>FoRetryCount</b> ='value'				
	<table border="1"> <thead> <tr> <th>Parameter</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><i>value</i></td> <td>Specifies the number of times you want PowerBuilder to try to fail over.</td> </tr> </tbody> </table>	Parameter	Description	<i>value</i>	Specifies the number of times you want PowerBuilder to try to fail over.
Parameter	Description				
<i>value</i>	Specifies the number of times you want PowerBuilder to try to fail over.				
Default value	FoRetryCount = '10'				
Usage	You can enter a failover retry value only if you have enabled failover.  This parameter cannot be set dynamically. The value set when the connection is made remains in effect until it is disconnected.				
Examples	To tell PowerBuilder to try 20 times to fail over: <ul style="list-style-type: none"> <li>• <b>Database profile</b> Enter the value 20 in the Retry Count box on the Network tab in the Database Profile Setup dialog box.</li> <li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm="FoRetryCount=' 20 ' "</pre> </li> </ul>				
See also	SvrFailover				

## FormatArgsAsExp

**Description** Controls whether PowerBuilder converts a DataWindow object retrieval argument of decimal datatype to scientific (exponential) notation if the argument exceeds 12 digits but has fewer than 16 digits. If FormatArgsAsExp is set to Yes (the default), PowerBuilder performs this conversion.

---

### When to specify FormatArgsAsExp

You must specify a value for FormatArgsAsExp *before* connecting to the database.

---

**Applies to** DIR Sybase DirectConnect  
JDB JDBC  
ODBC interface  
O84 Oracle 8.x and Oracle8i  
O90 Oracle9i  
O10 Oracle 10g  
SYC and SYJ Sybase Adaptive Server Enterprise



## Syntax

**FormatArgsAsExp= 'value'**

Parameter	Description
<i>value</i>	Specifies whether you want PowerBuilder to convert a DataWindow or report retrieval argument of decimal datatype to scientific (exponential) notation if the argument exceeds 12 digits but has fewer than 16 digits. Values are: <ul style="list-style-type: none"> <li>• <b>Yes</b> PowerBuilder converts a retrieval argument of decimal datatype to scientific notation if it exceeds 12 digits but has fewer than 16 digits.</li> <li>• <b>No</b> (Default) PowerBuilder leaves the retrieval argument as a decimal and does not perform the default conversion to scientific notation if it exceeds 12 digits but has fewer than 16 digits.</li> </ul>

## Default value

FormatArgsAsExp = 'No'

## Usage

*When to use* The setting of FormatArgsAsExp might affect the speed of data retrieval in your DataWindow objects, especially if you are accessing large databases.

If FormatArgsAsExp is set to Yes, PowerBuilder converts retrieval arguments of type decimal to scientific notation if the argument exceeds 12 digits but has fewer than 16 digits. Some DBMS optimizers might interpret the resulting scientific notation as a different datatype and scan all rows in the table to find it. This can slow data retrieval if, for example, you are accessing a DB2 database with many large tables.

Setting FormatArgsAsExp to No tells PowerBuilder to leave the retrieval argument as a decimal and not convert it to scientific notation. This speeds data retrieval for large databases.

**Retrieval argument size limited**

The FormatArgsAsExp parameter is relevant only if a retrieval argument of type decimal has fewer than 16 digits.

## Examples

To tell PowerBuilder to convert a retrieval argument exceeding 12 digits but with fewer than 16 digits to scientific notation:

- **Database profile** Check the Format Arguments in Scientific Notation check box on the Syntax tab (or Transaction tab in the case of the DIR interface) in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="FormatArgsAsExp='Yes' "
```

## GetConnectionOption

**Description** Specifies how EAServer should behave if all connections in a cache are being used. This parameter applies *only* when a PowerBuilder custom class user object is deployed as an EAServer component.

**Applies to** JDB JDBC  
ODBC  
O84 Oracle 8.x and Oracle8i  
O90 Oracle9i  
O10 Oracle 10g  
SYJ Sybase Adaptive Server Enterprise

**Syntax** **GetConnectionOption** = '*value*'

Parameter	Description
<i>value</i>	Specifies how EAServer should behave if all connections in a cache are being used. Values are: <ul style="list-style-type: none"><li>• <b>JAG_CM_FORCE</b> (Default) Allocates and opens a new connection. The new connection is not cached and is deallocated when the connection is explicitly or implicitly closed by the component.</li><li>• <b>JAG_CM_NOWAIT</b> Fails with an error if no connection can be made.</li><li>• <b>JAG_CM_WAIT</b> Does not return until a connection is available.</li></ul>

**Default value** GetConnectionOption = 'JAG\_CM\_FORCE'

**Usage** This parameter cannot be set dynamically. The value set when the connection is made remains in effect until it is disconnected.

---

### Using the SYJ interface

Sybase EAServer uses a slightly different version of the CT-Lib software. Therefore, *at runtime*, you need to use the SYJ database interface rather than SYC to connect to an Adaptive Server Enterprise database. The SYJ Database Profile Setup dialog box provides a convenient way to set the appropriate connection parameters and then copy the syntax from the Preview tab into the script for your Transaction object.

You cannot use the SYJ interface, however, to connect to the database in the PowerBuilder development environment. Therefore, *during the development phase* (before the component has been deployed to EAServer), you must use SYC to connect to the database.

---

For information on how to use PowerBuilder to build EAServer components, see *Application Techniques*.

**Examples**

On the EAServer tab in the Database Profile Setup dialog box, select JAG\_CM\_NOWAIT from the Get Connection Option drop-down list. The PowerScript syntax for the GetConnectionOption parameter displays on the Preview tab:

```
SQLCA.DBParm = "GetConnectionOption = 'JAG_CM_NOWAIT' "
```

Copy the syntax from the Preview tab into your script.

**See also**

CacheName  
ReleaseConnectionOption  
UseContextObject

**Host****Description**

If your DBMS supports it, specifies the workstation name when connecting to the database in PowerBuilder. The Host parameter lets you assign any 10-character label to identify the process you are about to create when you connect to the database. This label helps you distinguish your process from others running on the database server.

**When to specify Host**

You must specify the Host parameter *before* connecting to the database in PowerBuilder.

**Applies to**

SYC Sybase Adaptive Server Enterprise

**Syntax**

**Host** = '*workstation\_name*'

**Default value**

None

**Usage**

When you specify a value for Host, PowerBuilder sets the CS\_HOSTNAME connection property to the workstation name you specify.

The value you specify for the Host parameter displays in the hostname column of the MASTER.DBO.SYSPROCESSES table in a SQL Server database. How you use the Host parameter depends on the design of your PowerBuilder application.

For example, many sites want to secure their production tables so that updates are possible only through a specific application. To do this, you can grant explicit authority to the PowerBuilder application but *not* to users. The application prompts the user for an authorization ID and password, verifies it, and then connects to the database through a single application login ID. Only this application login ID has authorization to update production tables.

In this scenario, you can use the Host parameter to store the name of the user running the application.

#### Examples

**Example 1** To set the host name to Alan:

- **Database profile** Type the following in the Workstation Name box on the Network tab in the Database Profile Setup dialog box:

```
Alan
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "Host='Alan' "
```

**Example 2** You can use the Host and AppName parameters together to specify both the host name and the application name. To set the host name to Jane and the application name to Sales:

- **Database profile** Type Jane in the Workstation Name box and Sales in the Application Name box on the Network tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Host='Jane',AppName='Sales' "
```

**Example 3** The Host name in the preceding examples is hard coded. You can get the name dynamically using the Windows GetComputerNameA function. There is no PowerScript equivalent for this function. Here is the external function declaration:

```
FUNCTION boolean GetComputerNameA(ref string cname,ref  
long nbuf) LIBRARY "Kernel32.dll"
```

The following code in the Open event of the application uses an external function call to get the host name and set its value in the Host parameter. You must allocate sufficient space for the returned host name:

```
string ls_compname  
long ll_buf  
ll_buf = 25  
  
ls_compname = space(ll_buf)  
GetComputerNameA(ls_compname, ll_buf)
```

```
// Profile mysyb
SQLCA.DBMS = "SYC Adaptive Server Enterprise"
SQLCA.Database = "mydata"
SQLCA.LogPass = "mylogpass"
SQLCA.ServerName = "mysybsvr"
SQLCA.LogId = "mylogid"
SQLCA.AutoCommit = False
SQLCA.DBParm = "Host='" + ls_compname + "'"

Connect using SQLCA;
```

See also `AppName`

## HostReqOwner

**Description** Specifies the name of the host request library defined in a DB2/MVS database.

---

### When to specify HostReqOwner

You must specify the HostReqOwner parameter *before* connecting to the database.

---

**Applies to** DIR Sybase DirectConnect (applies only to Access Service for DB2/MVS and Open ServerConnect™)

**Syntax** `HostReqOwner = 'owner_id'`

**Default value** `HostReqOwner = 'Sybase'`

**Usage** The host request library is a special DB2 table that stores host-resident requests. A host-resident request is a SQL statement that a client application can execute as a procedure. If you do not use Sybase as the owner name for this host request library, you should set the HostReqOwner parameter to an appropriate name for your site.

---

### TRS Support

The HostReqOwner parameter is not applicable to DirectConnect TRS connections.

---

**Examples** To set the name of your host request library to Stratus:

- **Database profile** Type `Stratus` in the Host Request Lib Owner box on the System tab in the Database Profile Setup dialog box.

- **Application** Type the following in code:

```
SQLCA.DBParm="HostReqOwner='Stratus' "
```

See also

UseProcSyntax  
TRS

## IdentifierQuoteChar

Description

Specifies the single quote character you want PowerBuilder to use to delimit the names of identifiers (tables, columns, indexes, and constraints) when it generates SQL statements. PowerBuilder uses the quote character you specify instead of the default quote character returned by your driver or data provider.

---

### DelimitIdentifier must be set to Yes

In order for IdentifierQuoteChar to take effect, the DelimitIdentifier parameter must be set to Yes. Otherwise, PowerBuilder's default behavior is *not* to delimit identifiers in SQL statements and to ignore any value specified for IdentifierQuoteChar.

---

Applies to

ADO.NET  
JDB JDBC  
ODBC (if driver and back-end DBMS support this feature)  
OLE DB

Syntax

**IdentifierQuoteChar** = '*quote\_character*'

Parameter	Description
<i>quote_character</i>	The single character you want PowerBuilder to use instead of your driver's or data provider's default quote character to delimit the names of identifiers in SQL statements.

Default value

None

PowerBuilder searches the following in this order to determine the IdentifierQuoteChar value:

- 1 The section for your database profile in the PowerBuilder initialization file (in the development environment) or the value of the Transaction object DBParm property (in a PowerBuilder application)
- 2 The section for your ODBC driver in the PBODB105 initialization file or the section for your JDBC driver in the registry

If PowerBuilder does not find an IdentifierQuoteChar value in these locations, it makes a SQLGetInfo call to your driver to return the default SQL\_IDENTIFIER\_QUOTE\_CHAR value.

---

#### When using the OLE DB interface

If no value is specified for the IdentifierQuoteChar parameter, PowerBuilder does not use a quote character.

---

#### Usage

By default, some drivers return quote characters that do not work with PowerBuilder's parsing routines, such as the backquote character (`). As a result, delimiting is turned off for these drivers in PowerBuilder.

However, if you paint SQL statements containing identifiers that require delimiters, syntax errors can occur if you are using a driver for which delimiting is turned off. To avoid such errors, set IdentifierQuoteChar to override the driver's default quote character.

#### Examples

To specify *c* as the quote character you want PowerBuilder to use to delimit identifiers in SQL statements:

- **Database profile** Type *c* in the Identifier Quote Character box on the Syntax tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="IdentifierQuoteChar='c'"
```

#### See also

DelimitIdentifier

## ImpersonationLevel

**Description** Specifies the level of impersonation that the data server is allowed to use when impersonating its OLE DB data provider and PowerBuilder. This parameter applies only to network connections other than Remote Procedure Call (RPC) connections.

---

### When to specify ImpersonationLevel

You must specify the ImpersonationLevel parameter *before* connecting to the database.

---

**Applies to** OLE DB

**Syntax** `ImpersonationLevel = 'value'`

Parameter	Description
<i>value</i>	<p>Specifies the level of impersonation. Values are:</p> <ul style="list-style-type: none"> <li>• <b>Not set</b> No level of impersonation is selected.</li> <li>• <b>Anonymous</b> The client is anonymous to the server and the server process cannot obtain identification information about the client and cannot impersonate the client.</li> <li>• <b>Delegate</b> The process can impersonate the client's security context while acting on behalf of the client. The server process can also make outgoing calls to other servers while acting on behalf of the client.</li> <li>• <b>Identify</b> The server can obtain the client's identity. The server can impersonate the client for ACL checking but cannot access system objects as the client.</li> <li>• <b>Impersonate</b> The server process can impersonate the client's security context while acting on behalf of the client. This information is obtained when the connection is established, not on every call.</li> </ul>

**Default value** ImpersonationLevel = 'Not set'

**Examples** To set a level of impersonation to anonymous:

- **Database profile** On the Security tab in the Database Profile Setup dialog box, select Anonymous from the Impersonation Level drop-down list.
- **Application** Type the following in code:

```
SQLCA.DBParm =
"IMPERSONATIONLEVEL='DB_IMP_LEVEL_ANONYMOUS' "
```

**See also** [DataLink](#)



## INET\_DBPATH

**Description** Specifies the Informix DBPATH setting. The DBPATH environment variable identifies a list of directories that contain Informix databases. INET\_DBPATH typically specifies the location of Informix databases if this is *other* than in a directory on the database server.

**Applies to** IN9 Informix

**Syntax** `INET_DBPATH = 'server_db_path'`

Parameter	Description
<code>server_db_path</code>	The name of the directory containing Informix databases

**Default value** By default, PowerBuilder uses the value specified for DBPATH in the Informix.INI configuration file.

**Examples** **Example 1** To specify that the directory /HOME/Informix contains Informix databases:

- **Database profile** Type the following in the Database Path box on the Network tab in the Database Profile Setup dialog box:

```
/home/Informix
```

- **Application** Type the following in code:

```
SQLCA.DBParm="INET_DBPATH='/home/Informix'"
```

**Example 2** You can specify values for INET\_DBPATH, INET\_PROTOCOL, and INET\_SERVICE together. To specify that the directory /Informix contains Informix databases and that you want to connect using the SE9 service and the TCP/IP network protocol:

- **Database profile** Type /Informix in the Database Path box, SE9 in the Service Name box, and tcp-ip in the Protocol Type box on the Network tab in the Database Profile Setup dialog box.

- **Application** Type the following on a single line in code:

```
SQLCA.DBParm="INET_DBPATH='/Informix',  
INET_SERVICE = 'se9',INET_PROTOCOL = 'tcp-ip'"
```

**See also** INET\_PROTOCOL  
INET\_SERVICE

## INET\_PROTOCOL

**Description** Specifies the network protocol that the Informix client software uses to communicate with a remote Informix version 9.x database server.

**Applies to** IN9 Informix

**Syntax** `INET_PROTOCOL = 'network_protocol'`

Parameter	Description
<i>network_protocol</i>	A string that specifies the name of the network protocol used by the Informix client software.  For information about the correct network protocol for your site, see your Informix system administrator.

**Default value** By default, PowerBuilder uses the network protocol specified in the Informix.INI configuration file.

**Examples** **Example 1** To specify that Informix client software uses the Novell IPX/SPX network protocol:

- **Database profile** Type `ipx` in the Protocol Type box on the Network tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="INET_PROTOCOL='ipx' "
```

**Example 2** You can specify values for `INET_DBPATH`, `INET_PROTOCOL`, and `INET_SERVICE` together. To specify that the directory `/Informix` contains Informix databases, and that you want to connect using the `SE9` service and the `TCP/IP` network protocol:

- **Database profile** Type `/Informix` in the Database Path box, `SE9` in the Service Name box, and `tcp-ip` in the Protocol Type box on the Network tab in the Database Profile Setup dialog box.
- **Application** Type the following on a single line in code:

```
SQLCA.DBParm="INET_DBPATH='/Informix',INET_SERVICE='se9',INET_PROTOCOL='tcp-ip' "
```

See also `INET_DBPATH`  
`INET_SERVICE`

## INET\_SERVICE

**Description** Specifies the name of the service that a remote Informix database server uses to listen to all incoming requests from client applications.

**Applies to** IN9 Informix

**Syntax** `INET_SERVICE = 'service_name'`

Parameter	Description
<i>service_name</i>	A string that specifies the name of the service that a remote Informix database server uses to listen to incoming requests For information about the correct service name for your site, see your Informix system administrator.

**Default value** By default, PowerBuilder uses the service name specified in the Informix.INI configuration file.

**Examples** **Example 1** To specify that your Informix database server uses the sqlexec service name:

- **Database profile** Type `sqlexec` in the Service Name box on the Network tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="INET_SERVICE='sqlexec' "
```

**Example 2** You can specify values for INET\_DBPATH, INET\_PROTOCOL, and INET\_SERVICE together. To specify that the directory /Informix contains Informix databases, and that you want to connect using the SE9 service and the TCP/IP network protocol:

- **Database profile** Type /Informix in the Database Path box, SE9 in the Service Name box, and tcp-ip in the Protocol Type box on the Network tab in the Database Profile Setup dialog box.
- **Application** Type the following on a single line in code:

```
SQLCA.DBParm="INET_DBPATH='/Informix',INET_SERVICE='se9',INET_PROTOCOL='tcp-ip' "
```

**See also** INET\_DBPATH  
INET\_PROTOCOL

## Init\_Prompt

Description Specifies whether you want to be prompted during initialization.

---

### When to specify Init\_Prompt

You must specify the Init\_Prompt parameter *before* connecting to the database.

---

Applies to OLE DB

Syntax **Prompt = 'value'**

Parameter	Description
<i>value</i>	Specifies whether you want to be prompted during initialization. Values are: <ul style="list-style-type: none"><li>• <b>Not set</b> Do not prompt.</li><li>• <b>Always</b> Always prompt for initialization information.</li><li>• <b>If needed</b> Prompt only if more information is needed.</li><li>• <b>If needed (required)</b> Prompt only if more information is needed. Do not allow the user to enter optional information.</li><li>• <b>Never</b> Do not prompt.</li></ul>

Default value Init\_Prompt = 'Not set'

Examples To specify that you want always to be prompted during initialization:

- **Database profile** Select Always from the Prompt drop-down list on the System tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm= " INIT_PROMPT= ' DBPROMPT_PROMPT ' "
```

See also DataLink

## InsertBlock

Description Specifies the number of rows that you want the Data Pipeline in PowerBuilder to insert at one time into a table in the destination database.

For instructions on using the Data Pipeline, see the *User's Guide*.

Applies to ODBC (only in Data Pipeline if driver and back-end DBMS support this feature)

Syntax

**InsertBlock** = *insert\_blocking\_factor*

Parameter	Description
<i>insert_blocking_factor</i>	The number of rows that you want the Data Pipeline to insert at one time into a table in the destination database, up to a maximum of 100 rows (Default = 100 rows). To turn off block inserting for an ODBC data source in the Data Pipeline, set InsertBlock to 1 or DisableBind to 1 in the database profile of the destination database.

Default value

InsertBlock = 100

Usage

*Requirements for using InsertBlock* To use the InsertBlock parameter, *all* of the following must be true:

- You are using an ODBC driver to access the destination database in the Data Pipeline.
- The destination database supports the use of bind variables. (For more about bind variables, see DisableBind.)
- The DisableBind parameter is not set to 1 (the default is 0) in the database profile of the destination database. This enables the default binding of input parameters to a compiled SQL statement in PowerBuilder.
- Maximum Errors is set to 1 in the Data Pipeline.

The Adaptive Server Anywhere ODBC driver and most PB DataDirect ODBC drivers meet the first two requirements.

To determine whether your ODBC driver meets these requirements, see the documentation that comes with your driver.

*Determining the InsertBlock value* PowerBuilder searches the following in this sequence to determine the value for InsertBlock:

- 1 The section for your database profile in the PowerBuilder initialization file
- 2 The section for your ODBC driver in the PBODB105 initialization file

If PowerBuilder does not find an InsertBlock value in these locations, it defaults to an insert blocking factor of 100 rows.

*What happens* When PowerBuilder finds a value for InsertBlock, the Data Pipeline batches the specified number of rows and inserts them with a single call to the ODBC driver you are using to access the destination database.

If you specify an InsertBlock value or Data Pipeline commit factor of fewer than 100 rows, the Data Pipeline batches and inserts the specified number of rows into the destination database. If you specify more than 100 rows, the Data Pipeline batches and inserts at most only 100 rows at one time.

The insert blocking factor that the Data Pipeline actually uses depends on the size of the data in each column inserted in the destination database. In addition, the Data Pipeline does not exceed 64K of data in the buffer for any one column.

*Turning off block inserting* To turn off block inserting for an ODBC data source in the Data Pipeline, you can do any of the following in the database profile of the destination database:

- Set the InsertBlock parameter to 1
- Set the DisableBind parameter to 1 (to disable default binding of input parameters to a compiled SQL statement)
- In the Data Pipeline, set Maximum Errors to a value other than 1

Examples

To set the insert blocking factor in the Data Pipeline to 50 rows:

- **Database profile** Type 50 in the Insert Blocking Factor box on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="InsertBlock=50"
```

See also

DisableBind

## IntegratedSecurity

Description

Specifies the name of the authentication service used by the data server to identify the user.

If this parameter is specified, none of the other OLE DB authentication parameters (CacheAuthentication, EncryptPassword, MaskPassword, PersistEncrypted, and PersistSecurityInfo) are needed and are ignored if specified.

---

### When to specify IntegratedSecurity

You must specify the IntegratedSecurity parameter *before* connecting to the database.

---

Applies to

OLE DB

Syntax	<b>IntegratedSecurity = 'value'</b>				
	<table border="1"> <thead> <tr> <th>Parameter</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><i>value</i></td> <td>A string specifying the name of the authentication service. If NULL, the default authentication service is used.</td> </tr> </tbody> </table>	Parameter	Description	<i>value</i>	A string specifying the name of the authentication service. If NULL, the default authentication service is used.
Parameter	Description				
<i>value</i>	A string specifying the name of the authentication service. If NULL, the default authentication service is used.				
Default value	None				
Examples	<p>To use an authentication service such as the Security Support Provider Interface (SSPI) for Windows NT:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Type the name of the authentication service in the Integrated Security box on the Security tab in the Database Profile Setup dialog box.</li> <li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm="IntegratedSecurity='SSPI' "</pre> </li> </ul>				

## Isolation

Description	<p>Sets the isolation level to use when connecting to the database.</p> <p>In multiuser databases, transactions initiated by different users can overlap. If these transactions access common data in the database, they can overwrite each other or collide.</p> <p>To prevent concurrent transactions from interfering with each other and compromising the integrity of your database, you can set the isolation level when you connect to the database. Isolation levels are used by .NET Framework data providers when performing a transaction.</p> <p>PowerBuilder uses the Isolation database parameter to allow you to set various database lock options. Each value corresponds to an isolation level defined in the .NET Framework.</p> <hr/> <p><b>When to specify the Isolation value</b>  You must set the Isolation value <i>before</i> you connect to the database. The Isolation value takes effect only when the database connection occurs. Changes made to the Isolation value after the connection occurs have no effect on the current connection.</p> <hr/>
Applies to	ADO.NET

Syntax

Isolation='value'

Parameter	Description
<i>value</i>	<p>A string specifying the isolation level. Values correspond to members of the .NET Framework IsolationLevel enumeration:</p> <ul style="list-style-type: none"> <li>• TC – Chaos</li> <li>• None specified – The default isolation level for the DBMS (Default)</li> <li>• RC – Read Committed</li> <li>• RU – Read Uncommitted</li> <li>• RR – Repeatable Read</li> <li>• TS – Serializable Transactions</li> </ul>

Default value

The default lock value depends on how your database is configured. For information, see your DBMS documentation.

Examples

**Example 1** To set the Isolation value to RC (Read Committed):

- **Development environment** Select Read Committed from the Isolation Level drop-down list in the Database Profile Setup dialog box.
- **Application** Type the following:

```
SQLCA.DBParm="Isolation='RC' "
```

---

**Using the example in code**

If you specify Isolation Level in your database profile, the syntax displays on the Preview tab in the Database Profile Setup dialog box. You can copy the syntax from the Preview tab into your code.

---

## JavaVM

Description

Specifies the version of the Java VM you want the JDBC database interface to use.

---

**When to specify JavaVM**

You must specify the JavaVM parameter *before* connecting to the database.

---

Applies to

JDB JDBC



Syntax	<b>JavaVM</b> = ' <i>value</i> '				
	<table border="1"> <thead> <tr> <th>Parameter</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><i>value</i></td> <td>Specifies the name of the Java VM. Values are: <ul style="list-style-type: none"> <li>• <b>Sun JRE 1.2</b> (Sun1.2)</li> <li>• <b>Sun JRE 1.3</b> (Sun1.3)</li> <li>• <b>Sun JRE 1.4</b> (Sun1.4)</li> </ul> </td> </tr> </tbody> </table>	Parameter	Description	<i>value</i>	Specifies the name of the Java VM. Values are: <ul style="list-style-type: none"> <li>• <b>Sun JRE 1.2</b> (Sun1.2)</li> <li>• <b>Sun JRE 1.3</b> (Sun1.3)</li> <li>• <b>Sun JRE 1.4</b> (Sun1.4)</li> </ul>
Parameter	Description				
<i>value</i>	Specifies the name of the Java VM. Values are: <ul style="list-style-type: none"> <li>• <b>Sun JRE 1.2</b> (Sun1.2)</li> <li>• <b>Sun JRE 1.3</b> (Sun1.3)</li> <li>• <b>Sun JRE 1.4</b> (Sun1.4)</li> </ul>				
Default value	JavaVM='Sun1.4'				
Usage	For consistent behavior, the same version of the Java VM used during development should be used at runtime.				
Examples	<p>To set the JavaVM parameter to Sun JRE 1.3:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Select Sun JRE 1.3 from the Java drop-down list on the Options tab in the Database Profile Setup dialog box.</li> <li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm = "JavaVM='Sun1.3'"</pre> </li> </ul>				

## KeepAlive

Description	Determines whether packets are sent to the database to ensure that the connection is still active.				
	<hr/> <p><b>When to specify KeepAlive</b> You must specify the KeepAlive parameter <i>before</i> connecting to the database.</p> <hr/>				
Applies to	SYC Sybase Adaptive Server Enterprise				
Syntax	KeepAlive = <i>value</i>				
	<table border="1"> <thead> <tr> <th>Parameter</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><i>value</i></td> <td>Specifies whether the Open Client/Server CS_CON_KEEPALIVE property is set for your connection. Values are: <ul style="list-style-type: none"> <li>• <b>1</b> (Default) CS_CON_KEEPALIVE property is set.</li> <li>• <b>0</b> CS_CON_KEEPALIVE property is not set.</li> </ul> </td> </tr> </tbody> </table>	Parameter	Description	<i>value</i>	Specifies whether the Open Client/Server CS_CON_KEEPALIVE property is set for your connection. Values are: <ul style="list-style-type: none"> <li>• <b>1</b> (Default) CS_CON_KEEPALIVE property is set.</li> <li>• <b>0</b> CS_CON_KEEPALIVE property is not set.</li> </ul>
Parameter	Description				
<i>value</i>	Specifies whether the Open Client/Server CS_CON_KEEPALIVE property is set for your connection. Values are: <ul style="list-style-type: none"> <li>• <b>1</b> (Default) CS_CON_KEEPALIVE property is set.</li> <li>• <b>0</b> CS_CON_KEEPALIVE property is not set.</li> </ul>				
Default value	KeepAlive=1				

Usage	KeepAlive sets the value of the Sybase CT-Lib connection property CS_CON_KEEPAALIVE to true or false. The default setting ensures that your connection is alive by sending packets to the database when the connection is idle. Set the value of this property to false for mobile clients that do not maintain constant connections.
Examples	<p>To set the KeepAlive value to 0 when you do not want to maintain a connection:</p> <ul style="list-style-type: none"><li>• <b>Database profile</b> Clear the Keep Connection Alive check box on the Network tab page.</li><li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm="KeepAlive=0"</pre></li></ul>

## Language

Description	<p>For those interfaces that support it, specifies the language you want to use when connecting to your target database.</p> <hr/> <p><b>When to specify Language</b> You must specify the Language parameter <i>before</i> connecting to the database. The Language setting takes effect when you connect to the database.</p> <hr/>
Applies to	<p>DIR Sybase DirectConnect SYC Sybase Adaptive Server Enterprise</p>
Syntax	<b>Language</b> = ' <i>language_name</i> '
Default value	None
Usage	<p>When you specify a value for Language, PowerBuilder:</p> <ul style="list-style-type: none"><li>• Allocates a CS_LOCALE structure for this connection</li><li>• Sets the CS_SYB_LANG value to the language you specify</li><li>• Sets the SQL Server CS_LOC_PROP connection property with the new locale information</li></ul> <p>If you have previously set a value for the Locale parameter, which includes settings for the language and character set you want the Open Client software to use, you can override the language value by specifying a new value for the Language parameter and reconnecting to the database.</p>

*Unicode data access* PowerBuilder can access Unicode data in an Adaptive Server Enterprise (ASE) 12.5 or higher Unicode database or in Unicode columns in ASE 12.5 or higher. PowerBuilder converts between double-byte character set (DBCS) data and Unicode automatically, provided that the Language and CharSet parameters are set with DBCS values (or the Locale parameter is set with DBCS values).

For example:

```
Language = 'tchinese'
CharSet = 'big5'
```

#### Examples

To set the Language parameter to French:

- **Database profile** Type `French` in the Language box on the Connection tab or Regional Settings tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="Language='French' "
```

#### See also

CharSet  
Locale

## LCID

#### Description

Specifies the locale identifier that you want the OLE DB data provider to use.

---

#### When to specify LCID

You must specify the LCID parameter *before* connecting to the database.

---

#### Applies to

OLE DB

#### Syntax

**LCID** = '*lcid\_name*'

#### Default value

None

#### Usage

You specify the locale identifier at initialization. This provides a way for the data server to determine PowerBuilder's preferred locale language and character set. However, setting this parameter does not guarantee that all text returned to PowerBuilder is translated according to the locale ID.

Examples	<p>To set the locale to US English:</p> <ul style="list-style-type: none"> <li>• <b>Database profile.</b> Type the following in the LCID box on the System tab in the Database Profile Setup dialog box:             <pre>1033</pre> </li> <li>• <b>Application.</b> Type the following in code:             <pre>SQLCA.DBParm="LCID= ' 1033 ' "</pre> </li> </ul>
See also	<p>CharSet Language</p>

## Locale

Description	<p>Specifies the locale name that you want the Sybase Open Client software to use when connecting to a Sybase Adaptive Server Enterprise database or a database accessed through DirectConnect in PowerBuilder.</p>
-------------	---

---

### When to specify Locale

You must specify the Locale parameter *before* connecting to the database.

---

Applies to	<p>DIR Sybase DirectConnect SYC Sybase Adaptive Server Enterprise</p>
Syntax	<p><b>Locale</b> = '<i>locale_name</i>'</p>
Default value	<p>The default locale defined in your LOCALES.DAT file</p>
Usage	<p><i>Locales</i> Locales are stored as entries in a file named LOCALES.DAT. The LOCALES.DAT file contains information about the languages and character sets you are using with the Sybase Open Client software. The Sybase Open Client installation places the LOCALES.DAT file in the \$SYBASE\LOCALES directory.</p> <p>An entry in the LOCALES.DAT file has the following format:</p> <pre><b>locale</b> = <i>locale_name</i>, <i>language_name</i>, <i>character_set_name</i></pre> <p>For example:</p> <pre>locale = default, us_english, cp850 locale = enu, us_english, cp850 locale = fra, french, cp850</pre>

*Why set Locale parameter* Setting a value for the Locale parameter lets you use a locale *other than the default locale* when accessing an Adaptive Server Enterprise or DirectConnect database. If you do not set a value for Locale, Sybase Open Client uses the default locale defined in your LOCALES.DAT file.

*What happens* When you specify a value for the Locale parameter, PowerBuilder:

- Allocates a CS\_LOCALE structure for this connection
- Sets the CS\_LC\_ALL value to the locale name you specify
- Sets the SQL Server CS\_LOC\_PROP connection property with the new locale information

*Overriding Locale parameter* If you have previously set a value for the Locale parameter that includes settings for the language and character set you want to use, you can override the language or character set values by specifying new values for the Language or CharSet parameter and reconnecting to the database.

*Unicode data access* InfoMaker can access Unicode data in an ASE 12.5 Unicode database or in Unicode columns in ASE 12.5. InfoMaker converts between double-byte character set (DBCS) data and Unicode automatically, provided that the Locale parameter is set with DBCS values. For example, the Locale parameter should be set to chs or cht.

## Examples

To set the locale to *fra*:

- **Database profile** Type the following in the Locale box on the Regional Settings tab in the Database Profile Setup dialog box:

```
fra
```

- **Application** Type the following in code:

```
SQLCA.DBParm="Locale='fra' "
```

*What happens* Setting the Locale parameter to *fra* has the same effect as individually setting both the Language and CharSet parameters as follows:

```
Language='French'  
CharSet='cp850'
```

## See also

CharSet  
Language

## Location

**Description** Specifies the location of the data source to which you want your OLE DB data provider to connect. Typically the location is the database server name.

---

### When to specify Location

You must specify the Location parameter *before* connecting to the database.

---

**Applies to** OLE DB

**Syntax** **Location** = 'location\_name'

**Default value** None

**Usage** Implementation of the Location parameter varies depending on the OLE DB data provider you are using. For specific information, see the data provider documentation provided by the OLE DB vendor.

## Log

**Description** Specifies whether the database server should log updates of text and image data in the transaction log. By default, the database server logs updates of text and image data in the transaction log.

**Applies to** SYC and SYJ Sybase Adaptive Server Enterprise

**Syntax** **Log** = value

Parameter	Description
value	A value that specifies whether the database server should log updates of text and image data in the transaction log. Values are: <ul style="list-style-type: none"><li>• <b>0</b> Do not log text and image updates in the transaction log. Specify this value only if your database server allows you to disable logging.</li><li>• <b>1</b> (Default) Log text and image updates in the transaction log.</li></ul>

**Default value** Log = 1

**Usage** You should set the Log parameter to 0 only if your database server allows you to disable logging.

**Examples** To specify that PowerBuilder should *not* log text and image updates in the transaction log:

- **Database profile** Clear the Log Text and Image Updates check box on the System tab or Transaction tab in the Database Profile Setup dialog box.

- **Application.** Type the following in code:

```
SQLCA.DBParm="Log=0"
```

## LoginTimeout

**Description** Specifies the number of seconds the JDBC or ODBC driver should wait for a login request to a JDBC database or an ODBC data source.

**Applies to** JDB JDBC  
ODBC (if driver and back-end DBMS support this feature)

**Syntax** `LoginTimeout = value`

Parameter	Description
<i>value</i>	The number of seconds you want the driver to wait for a login request

**Default value** ODBC: LoginTimeout = 15; JDBC: LoginTimeout = 0

**Usage** If you set LoginTimeout to 0, PowerBuilder does not call the JDBC or ODBC driver to set the LoginTimeout value and instead waits the number of seconds specified by the JDBC or ODBC driver's client software. If you set LoginTimeout to a value greater than 0, PowerBuilder does call the JDBC or ODBC driver to set the LoginTimeout value.

**Examples** To set the LoginTimeout value to wait 60 seconds for a login request:

- **Database profile** Type 60 in the Login Timeout box on the Network tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="LoginTimeout=60"
```

## LowerCasIdent

**Description** Specifies whether PowerBuilder displays identifier names in lowercase.

**Applies to** DIR Sybase DirectConnect (applies only to DB2/MVS)

**Syntax** `LowerCasIdent = 'value'`

Parameter	Description
<i>value</i>	Specifies whether you want PowerBuilder to display identifier names in lowercase. Values are: <ul style="list-style-type: none"><li>• <b>Yes</b> Display identifier names in lowercase</li><li>• <b>No</b> (Default) Do not display identifier names in lowercase</li></ul>

Default value

LowerCaseIdent = 'No'

Usage

PowerBuilder displays identifier names in uppercase (the way they are stored in the database). The LowerCaseIdent parameter can be set only if the DelimitIdentifier parameter is set to No, indicating that PowerBuilder should not enclose table and column names in double quotes. If you try to enclose a table and column names in double quotes with identifier names in lowercase, the LowerCaseIdent parameter value is reset to the default value, and you receive a warning message.

---

### Migrating PBMDI and PBNET applications to PBDIR

If you are migrating an application that previously used the InformationConnect DB2 Gateway or Net-Gateway for DB2 interface to the DirectConnect for DB2/MVS database interface, you should set the LowerCaseIdent parameter value to Yes. This enables you to continue to use the Select painter to edit DataWindows.

---

Examples

To have PowerBuilder display identifier names in lowercase:

- **Database profile** Select the Display Identifiers In Lower Case check box on the Syntax tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="LowerCaseIdent='Yes' "
```

## MaskPassword

Description

Specifies whether you want PowerBuilder to mask your password automatically when connecting to an OLE DB data provider.

---

### When to specify MaskPassword

You must specify the MaskPassword parameter *before* connecting to the database.

---

Applies to

OLE DB



Syntax	<b>MaskPassword</b> = 'value'				
	<table border="1"> <thead> <tr> <th>Parameter</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><i>value</i></td> <td>Specifies whether you want PowerBuilder to mask your password. Values are: <ul style="list-style-type: none"> <li>• <b>True</b> Tells PowerBuilder to mask the password</li> <li>• <b>False</b> (Default) Tells PowerBuilder not to mask the password</li> </ul> </td> </tr> </tbody> </table>	Parameter	Description	<i>value</i>	Specifies whether you want PowerBuilder to mask your password. Values are: <ul style="list-style-type: none"> <li>• <b>True</b> Tells PowerBuilder to mask the password</li> <li>• <b>False</b> (Default) Tells PowerBuilder not to mask the password</li> </ul>
Parameter	Description				
<i>value</i>	Specifies whether you want PowerBuilder to mask your password. Values are: <ul style="list-style-type: none"> <li>• <b>True</b> Tells PowerBuilder to mask the password</li> <li>• <b>False</b> (Default) Tells PowerBuilder not to mask the password</li> </ul>				
Default value	MaskPassword = 'False'				
Examples	<p>To tell PowerBuilder to mask your password when connecting to an OLE DB data provider:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Select the Mask Password check box on the Security tab in the Database Profile Setup dialog box.</li> <li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm="MaskPassword=' True ' "</pre> </li> </ul>				
See also	DataLink EncryptPassword IntegratedSecurity PersistEncrypted				

## MaxConnect

Description	<p>Sets the maximum number of simultaneous connections you want to make when accessing a database.</p> <p>The default is 25 simultaneous connections. You can override this default by setting MaxConnect up to the maximum number of simultaneous connections configured on the database server.</p> <hr/> <p><b>When to specify MaxConnect</b> You must specify a value for the MaxConnect parameter <i>before</i> connecting to the database.</p> <hr/>				
Applies to	DIR Sybase DirectConnect SYC Sybase Adaptive Server Enterprise				
Syntax	<b>MaxConnect</b> = <i>value</i>				
	<table border="1"> <thead> <tr> <th>Parameter</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><i>value</i></td> <td>The maximum number of simultaneous connections you want to make when accessing a database</td> </tr> </tbody> </table>	Parameter	Description	<i>value</i>	The maximum number of simultaneous connections you want to make when accessing a database
Parameter	Description				
<i>value</i>	The maximum number of simultaneous connections you want to make when accessing a database				

Default value	MaxConnect = 25
Usage	<i>DirectConnect and SYC</i> MaxConnect sets the Sybase CT-Lib connection property CS_MAX_CONNECT to the number of simultaneous database connections you specify for a single CT-Lib context.
Examples	To set the MaxConnect value to a maximum of 50 simultaneous database connections: <ul style="list-style-type: none"><li>• <b>Database profile</b> Type 50 in the Maximum Client Library Connections box (when using the SYC interface) or the Maximum Connections For This Context box (when using the DIR interface). This check box is on the Network tab.</li><li>• <b>Application</b> Type the following in code:<pre>SQLCA.DBParm="MaxConnect=50"</pre></li></ul>

## MaxFetchBuffer

Description	Sets the maximum size of the buffer into which the DataWindow object can fetch rows from the database. Using the MaxFetchBuffer parameter with the Block parameter can improve performance when accessing a database in PowerBuilder.				
Applies to	O84 Oracle 8.x and Oracle8i O90 Oracle9i O10 Oracle 10g				
Syntax	<b>MaxFetchBuffer</b> = <i>buffersize</i> <table border="1"><thead><tr><th>Parameter</th><th>Description</th></tr></thead><tbody><tr><td><i>buffersize</i></td><td>The number of bytes the fetch buffer can hold.</td></tr></tbody></table>	Parameter	Description	<i>buffersize</i>	The number of bytes the fetch buffer can hold.
Parameter	Description				
<i>buffersize</i>	The number of bytes the fetch buffer can hold.				
Default value	5000000 (bytes)				

---

### Using the default buffer size

You should not have to set a non-default value for MaxFetchBuffer. In most cases, the default buffer size should meet your needs.

---

Usage	You can use the MaxFetchBuffer database parameter in conjunction with the Block database parameter to improve performance when the size of a row is very large.
-------	---

The size of the actual fetch buffer is the product of the value of the blocking factor and the size of the row. If the fetch buffer required by the blocking factor and the row size is greater than the value of MaxFetchBuffer, the value of the blocking factor is adjusted so that the buffer is not exceeded.

For example, if block = 500 and the row size is 10KB, the fetch buffer is 5000KB, which equals the default maximum buffer size.

You can set Block and MaxFetchBuffer dynamically in code after connecting to the database. MaxFetchBuffer cannot be set in the Database Profile Setup dialog box.

**Examples** The following example sets the maximum fetch buffer size to 6000KB and the blocking factor to 500:

```
SQLCA.DBParm = "MaxFetchBuffer=6000000,block=500"
```

**See also** Block (ODBC, OLE DB, and Oracle)

## MixedCase

**Description** Specifies whether you want connections to an Oracle database to be case sensitive or case insensitive.

By default, MixedCase is set to 0. This setting specifies a case-insensitive connection and assumes that all identifiers are uppercase. To make the Oracle connection case sensitive, set the MixedCase parameter to 1.

**Applies to** O84 Oracle 8.x and Oracle8i  
O90 Oracle9i  
O10 Oracle 10g

**Syntax** **MixedCase = value**

Parameter	Description
<i>value</i>	Specifies whether an Oracle database connection is case sensitive or case insensitive. Values are: <ul style="list-style-type: none"> <li><b>0</b> (Default) The Oracle database connection is case insensitive. It assumes that all identifiers are uppercase.</li> <li><b>1</b> The Oracle database connection is case sensitive. It supports mixed case, uppercase, and lowercase identifiers.</li> </ul>

**Default value** MixedCase = 0

**Usage** When you set the MixedCase parameter to 1 and define a primary key for a table in an Oracle database, all of the following must contain only uppercase letters:

- The name of the primary key
- The name of the table containing the primary key
- The names of any foreign keys that reference the primary key

**Examples** To make an Oracle database connection case sensitive:

- **Database profile** Select the Case Sensitive check box on the Connection tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="MixedCase=1"
```

## Mode

**Description** Specifies access permission to the OLE DB data provider.

---

### When to specify Mode

You must specify the Mode parameter *before* connecting to the database.

---

**Applies to** OLE DB

**Syntax** **Mode** = 'value'

Parameter	Description
<i>value</i>	Specifies access permission to the OLE DB data provider. Values are: <ul style="list-style-type: none"><li>• <b>Deny read share</b> Prevents other users from opening in read mode.</li><li>• <b>Deny write share</b> Prevents other users from opening in write mode.</li><li>• <b>Exclusive share</b> Prevents other users from opening in read/write mode.</li><li>• <b>No share deny</b> Neither read nor write access can be denied to other users.</li><li>• <b>Read/Write</b> Allows read/write access.</li><li>• <b>Read-only</b> Allows read access.</li><li>• <b>Write-only</b> Allows write access.</li></ul>

**Default value** None

- Examples To allow other users read/write access to the OLE DB data provider:
- **Database profile** On the Transaction tab in the Database Profile Setup dialog box, select Read/Write from the Mode list box.
  - **Application** Type the following in code:
 

```
SQLCA.DBParm="MODE='DB_MODE_READWRITE' "
```
- See also DataLink

## MsgTerse

**Description** Specifies whether PowerBuilder should display terse error messages for JDBC or ODBC drivers. A terse error message is one without the SQLSTATE = *nnnn* prefix, where *nnnn* is the number of the error message.

By default, PowerBuilder displays JDBC and ODBC error messages with the SQLSTATE prefix. To display error messages without the SQLSTATE prefix, set MsgTerse to 'Yes'.

**Applies to** JDB JDBC  
ODBC

**Syntax** `MsgTerse = 'value'`

Parameter	Description
<i>value</i>	Specifies whether PowerBuilder should display error messages without the SQLSTATE prefix. Values are: <ul style="list-style-type: none"> <li>• <b>Yes</b> Display error messages <i>without</i> the SQLSTATE prefix</li> <li>• <b>No</b> (Default) Display error messages <i>with</i> the SQLSTATE prefix</li> </ul>

**Default value** MsgTerse = 'No'

**Usage** You can set the MsgTerse parameter to 'Yes' to display shorter JDBC or ODBC error messages in PowerBuilder. This might be useful if space on your screen is limited.

For example, suppose you are using the Data Pipeline in PowerBuilder to pipe data to an Adaptive Server Anywhere ODBC database, and errors occur while you are executing the pipeline. If MsgTerse is set to 'No' (the default value), pipeline errors display in an Error dialog box *with* the SQLSTATE prefix (for example, SQLSTATE = 23000).

If you specify `MsgTerse = 'Yes'` in the database profile of the Adaptive Server Anywhere destination database, the Data Pipeline displays terse ODBC error messages *without* the SQLSTATE prefix.

For instructions on using the Data Pipeline, see the PowerBuilder *User's Guide*.

Examples

To specify that PowerBuilder should display terse error messages without the SQLSTATE prefix:

- **Database profile** Select the Display Terse Error Messages check box on the System tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="MsgTerse='Yes' "
```

## Namespace

Description

Specifies the .NET Framework data provider to be used to access data.

---

**When to specify Namespace**

You must specify the Namespace parameter *before* connecting to the database.

---

Applies to

ADO.NET

Syntax

**Namespace** = '*value*'

Parameter	Description
<i>value</i>	Specifies a namespace to be used as the data provider for an ADO.NET connection. Supported namespaces can be selected from the drop-down list.

Default value

None

Usage

The .NET Framework data provider for a given DBMS describes a collection of classes used to access a data source in that format in the managed space.

Examples

To specify that PowerBuilder should use the System.Data.OleDb namespace to connect to a database:

- **Database profile** Select System.Data.OleDb from the Namespace drop-down list on the General tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="Namespace='System.Data.OleDb' "
```

## NCharBind

**Description** Specifies whether PowerBuilder binds string variables in a program to an internal variable with the Oracle Char or Oracle NChar datatype.

**Applies to** ADO.NET (Oracle.DataAccess.Client only)  
O90 Oracle9i  
O10 Oracle 10g

**Syntax** **NCharBind** = *value*

Parameter	Description
<i>value</i>	Specifies whether PowerBuilder binds string variables in a program to an internal variable with the Char or NChar datatype. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> (Default) PowerBuilder binds string data as a Char datatype.</li> <li>• <b>1</b> PowerBuilder binds string data as an NChar datatype.</li> </ul>

**Default value** NCharBind=0

**Usage** By default, the Oracle drivers and the ADO.NET driver with the Oracle Data Provider for .NET (ODP.NET) bind the string parameters in statements such as the following as Char datatypes:

```
dw_1.Retrieve("stringvalue")

// Modify data in a DataWindow, then
dw_1.Update() // updating string value

// embedded SQL
update tbl set col1 = :strVar1 where col2 = :strVar2;
```

If the string parameters have NChar or NVarChar2 datatypes, set the NCharBind database parameter to 1 before executing statements like these. NCharBind is a dynamic parameter that can be set at any time.

With NCharBind=1, the Oracle drivers bind all string parameters to internal variables with the NChar datatype. If the string parameters are a mix of Char and NChar or NVarChar2 datatypes, set NCharBind=1 to ensure that the NChar data is bound correctly. If all string parameters have a Char datatype, set NCharBind=0 (the default), because binding a Char variable as an NChar datatype substantially downgrades the Oracle database driver's performance.

If you need NChar support in the development environment, set NCharBind to 1 to ensure that NChar data is processed correctly. At runtime, set NCharBind dynamically to avoid a downgrade in performance. Set NCharBind to 1 before processing NChar or NVarChar2 data, then reset it to 0.

Examples

To specify that string arguments should be bound as the NChar datatype:

- **Database profile** Select the NChar Bind box on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "NCharBind=1"
```

## NumbersInternal

Description

Specifies that numbers should be retrieved from the database using Oracle's internal 21-byte binary NUMBER datatype format instead of using OCI strings. The NumbersInternal parameter is relevant *only* when you are accessing an Oracle database configured with an EBCDIC character set or other non-ASCII character set.

---

**When to specify NumbersInternal**

You must specify the NumbersInternal parameter *before* connecting to the database.

---

Applies to

O84 Oracle 8.x and Oracle8i  
O90 Oracle9i  
O10 Oracle 10g

Syntax

**NumbersInternal** = *value*

Parameter	Description
<i>value</i>	Specifies that numbers should be retrieved using Oracle's internal 21-byte binary NUMBER datatype format. Values are: <ul style="list-style-type: none"><li>• <b>0</b> (Default) Do not retrieve numbers in internal format.</li><li>• <b>1</b> Retrieve numbers in internal format.</li></ul>

Default value

NumbersInternal = 0

Usage

In addition to specifying that numbers be retrieved from the database using Oracle's internal 21-byte binary NUMBER datatype format, the NumbersInternal parameter also provides an internal algorithm for deciphering the result.



- Examples To specify that you want numbers to be retrieved using Oracle's internal format:
- **Database profile.** Select the Retrieve Numbers in Internal Format check box on the Syntax tab in the Database Profile Setup dialog box.
  - **Application.** Type the following in code:
 

```
SQLCA.DBParm="NumbersInternal=1"
```

## NumericFormat

- Description If supported by the DBMS or back-end database, setting NumericFormat tells the driver to do special formatting of numeric strings in SQL syntax. This formatting affects how PowerBuilder generates numeric values in the SQL syntax it internally builds in DataWindow objects and sends to your database.
- Applies to JDB JDBC  
ODBC
- Syntax The syntax you use depends on the back-end DBMS you are accessing and how you want to format the numeric string.
- The following are typical syntax examples for Oracle databases that format a numeric string with a comma as the decimal separator. (See the Examples section for information about how PowerBuilder generates numeric values in the SQL syntax it builds and sends to the database.)
- In the PowerBuilder development environment, the Database Profile Setup dialog box inserts special characters (quotes) where needed, so you can specify just the NumericFormat value (%s in this example).
- In code, you must use the following syntax:
- IBM DB2 syntax** If you are accessing an IBM DB2 database through the ODBC interface, use the following syntax for NumericFormat. Note the use of *one single quote* at the beginning and end of the string:
- ```
NumericFormat='%s,%s'
```
- Oracle JDBC or ODBC syntax** If you are accessing an Oracle database through the JDBC or ODBC interface, use the following syntax for NumericFormat. Note the use of *three single quotes* at the beginning and end of the string:
- ```
NumericFormat = '''%s,%s'''
```

Parameter	Description
'	<b>IBM DB2 syntax</b> Type a single open quote. PowerBuilder returns no open quote in the SQL syntax it builds and sends to the database, as required by IBM DB2 databases.
'''	<b>Oracle, JDBC, or ODBC syntax</b> Type three single open quotes. PowerBuilder parses the second and third quotes as one single open quote in the SQL syntax it builds and sends to the database.
%s	Represents one or more digits to the <i>left of the decimal</i> in the numeric string. PowerBuilder substitutes this value with the digits to the left of the decimal when it builds the SQL syntax.
,	Represents the decimal separator character (in this case a comma).
%s	Represents one or more digits to the <i>right of the decimal</i> in the numeric string. PowerBuilder substitutes this value with the digits to the right of the decimal when it builds the SQL syntax.
'	<b>IBM DB2 syntax</b> Type one single closed quote. PowerBuilder returns no closed quote in the SQL syntax it builds and sends to the database, as required by IBM DB2 databases.
'''	<b>Oracle, JDBC, or ODBC syntax</b> Type three single closed quotes. PowerBuilder parses the first and second quotes as one single closed quote in the SQL syntax it builds and sends to the database.

Default value           None

Usage                    *When to set NumericFormat*   In general, you should *not* need to set the NumericFormat parameter. Most back-end DBMSs do not require that the driver do special formatting of numeric strings in SQL syntax. However, some databases might require special formatting, such as an IBM DB2/MVS database server configured to use a comma as the decimal separator.

In these cases, setting NumericFormat allows you to generate numeric values with special formatting in the SQL syntax that PowerBuilder builds in DataWindow objects and sends to your database. For example, if the decimal separator for your DBMS is a comma, you might want to set NumericFormat as shown in the Examples section below to use a comma as the decimal delimiter in the SQL syntax sent to your database.

Examples                **Example 1 (IBM DB2 syntax)** This example shows how to specify that you want PowerBuilder to generate two numeric values in the format *125,50* and *4,0*. PowerBuilder uses the comma as a decimal separator in the SQL syntax it builds in DataWindow objects and sends to an IBM DB2 database.

- **Database profile** Type the following in the Numeric Format box on the Syntax tab in the Database Profile Setup dialog box:

```
%s,%s
```

- **Application** Type the following in code:

```
SQLCA.DBParm="NumericFormat='%s,%s' "
```

*What happens* PowerBuilder internally builds the following SQL INSERT statement in the DataWindow object and sends the syntax to your database. PowerBuilder returns no quotes in the SQL syntax.

```
INSERT INTO MYTABLE (a, b)
VALUES (125,50, 4,0)
```

**Example 2 (Oracle JDBC or ODBC syntax)** This example shows how to specify that you want PowerBuilder to generate two numeric values in the format '125,50' and '4,0'. PowerBuilder uses the comma as a decimal separator in the SQL syntax it builds in DataWindow objects and sends to an Oracle database.

- **Database profile** Type the following in the Numeric Format box on the Syntax tab in the Database Profile Setup dialog box:

```
%s,%s
```

- **Application** Type the following in code:

```
SQLCA.DBParm="NumericFormat='''%s,%s'''"
```

*What happens* PowerBuilder internally builds the following SQL INSERT statement in the DataWindow object and sends the syntax to your database. PowerBuilder returns single quotes in the SQL syntax.

```
INSERT INTO MYTABLE (a, b)
VALUES ('125,50', '4,0')
```

See also

DecimalSeparator

## ObjectMode

Description

Allows PowerBuilder to turn off the Oracle Call Interface (OCI) object mode. By default, PowerBuilder sets the mode parameter of OCIInitialize(), the first OCI call in any OCI application, to OCI\_OBJECT. When object mode is on, your application can define and use new database object types. However, if your application uses an Oracle 8.1.7 database, it cannot perform external OCI activity in a child OCI environment, such as calling an external DLL to execute queries in an Oracle 8.1.7 database, when object mode is on.

Applies to O84 Oracle 8.x and Oracle8i  
 O90 Oracle9i  
 O10 Oracle 10g

Syntax ObjectMode = *value*

Parameter	Description
<i>value</i>	Specifies whether object mode is enabled or not. Values are: <ul style="list-style-type: none"> <li>• <b>Yes</b> (Default) Use object mode.</li> <li>• <b>No</b> Do not use object mode.</li> </ul>

Default value Yes

Usage To turn ObjectMode off, clear the ObjectMode check box on the Connection tab of the Database Profile Setup dialog box, or set ObjectMode to “No” in a script.

Examples To specify that you want ObjectMode disabled:

- **Database profile** Deselect the ObjectMode check box on the Connection tab of the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="ObjectMode='No' "
```

## ODBCU\_CONLIB

Description Specifies whether EAServer establishes an ODBC connection cache in ANSI or Unicode mode.

This parameter applies *only* when a PowerBuilder custom class user object or JSP page is deployed to EAServer.

Applies to ODBC

Syntax ODBC\_CONLIB = *value*

Parameter	Description
<i>value</i>	Specifies whether EAServer establishes an ODBC connection cache in ANSI or Unicode mode. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Establish a connection in ANSI mode</li> <li>• <b>1</b> Establish a connection in Unicode mode</li> </ul>

Default value ODBC\_CONLIB = 0

**Usage** Set this parameter to 1 to specify that the EAServer JAG\_CM\_CONLIB connection cache property should be set to ODBC to establish an ODBC connection in Unicode mode.

**Examples** To specify that you want a Unicode connection cache:

- **Database profile** Select the Enable Unicode Connection check box on the EAServer/COM+ page of the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="ODBC_CONLIB=1"
```

## OJSyntax

**Description** Specifies how PowerBuilder formats the SQL syntax for outer joins for the database back end you are accessing.

**Applies to** ADO.NET  
Informix 9  
JDB JDBC  
ODBC  
OLE DB  
O90 Oracle9i  
O10 Oracle 10g  
SYC Sybase Adaptive Server Enterprise

**Syntax** **OJSyntax** = *value*

Parameter	Description
<i>value</i>	Specifies how you want SQL syntax to be formatted. Values are: <ul style="list-style-type: none"> <li>• <b>ANSI_Escape</b> Apply ANSI standards and enclose the outer joins in escape notation { oj ... } that is parsed by the driver and replaced with DBMS-specific grammar.</li> <li>• <b>ANSI</b> Apply ANSI standards.</li> <li>• <b>PB</b> Maintain rules that applied to PowerBuilder 7.</li> </ul>

**Default value** OJSyntax = ANSI for IN9 and SYC, OJSyntax = ANSI\_ESCAPE for ADO.NET, JDBC, ODBC, and OLE DB, OJSyntax = PB for O90 and O10.

**Usage** All PowerBuilder database interfaces provide support for ANSI SQL-92 outer join SQL syntax generation. PowerBuilder supports both left and right outer joins in graphics mode and full outer and inner joins in syntax mode.

You must set the OJSyntax parameter to indicate the version of outer join SQL syntax you want PowerBuilder to generate. For ADO.NET, JDBC, ODBC, and OLE DB, the default is ANSI\_Escape and can be reset to ANSI or PB (native). For IN9 and SYC, the default is ANSI and can be reset to PB. For O90 and O10, the default is PB, which means use Oracle native outer join syntax, and can be reset to ANSI.

OJSyntax is a dynamic parameter in all database drivers that support it. It can therefore be changed at any time during the life of a database connection with a statement such as:

```
SQLCA.DBParm="OJSyntax='ANSI_ESCAPE' "
```

*Define outer joins in the SQL painter for portability* When you define an outer join SELECT statement graphically in the SQL painter, the DataWindow object stores the SQL in pseudocode. At runtime, the outer join syntax is generated based on the current OJSyntax parameter setting. This provides some degree of portability for DataWindow objects among multiple DMBSs.

When you define an outer join SELECT statement in syntax mode, the DataWindow object stores the SQL as syntax. This syntax is used without modification at runtime. The OJSyntax parameter setting does *not* affect the SQL.

*Using native outer join syntax* The option PB generates native outer join syntax. It is available for ODBC and OLE DB only if PBOuterJoin and PBOuterJoinOperator syntax entries are set in the appropriate SYNTAX section for your DBMS in the *Sybase\Shared\PowerBuilder\pbodb105.ini* file.

The PB option is available for JDBC only if PBOuterJoin and PBOuterJoinOperator syntax entries are set in the Windows registry in the appropriate key for your DBMS in the *HKEY\_CURRENT\_USER\Software\Sybase\PowerBuilder\10.5\pbjdbc* key. This key is not installed by default. See the *egreg.txt* file in *Sybase\Shared\PowerBuilder* for an example of a registry file you could execute to add or change PowerBuilder JDBC settings for your DBMS.

When you migrate applications from PowerBuilder 7 and earlier versions of PowerBuilder, using ANSI outer join syntax might produce errors, depending on how the joins were defined in the painter. If a table is joined to multiple other tables with right outer joins, a valid ANSI outer join statement cannot be generated.

For more information about outer joins, see the section on using ANSI outer joins in the PowerBuilder *User's Guide*.

*OJSyntax* does not apply to *DIR*. For one database interface, *DIR*, the database connection always uses ANSI outer join SQL syntax.

## Examples

To set the value of *OJSyntax*:

- **Database profile** Select the appropriate value from the Outer Join Syntax drop-down list on the Syntax tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="OJSyntax='ANSI' "
```

## OraMTSConFlgs

## Description

Specifies the behavior of a transactional PowerBuilder component deployed to COM+. This parameter applies *only* when a PowerBuilder custom class user object is deployed as a COM+ component and is connecting to an Oracle 8.1.5 or higher database.

## Applies to

O84 Oracle 8.x and Oracle8i (8.1.5 or higher database connections only)  
O90 Oracle9i

## Syntax

**OraMTSConFlgs** = '*value*'

Parameter	Description
<i>value</i>	<p>Specifies the behavior of a transactional component deployed to COM+. Values are:</p> <ul style="list-style-type: none"> <li>• <b>All Default</b> (Default) Obtains a pooled connection and enlists the connection in any COM+ transaction, if one exists (ORAMTS_CFLG_ALLDEFAULT).</li> <li>• <b>No Implicit Enlistment</b> Obtains a pooled connection but does not enlist the resource in any COM+ transaction even if the component is transactional (ORAMTS_CFLG_NOIMPLICIT).</li> <li>• <b>Unique Server Session</b> Requests a single OCI session per OCI Server. Since multiplexing is not supported in Version 8.1.5, this option is always used (ORAMTS_CFLG_UNIQUESEVR).</li> <li>• <b>SYSDBA Login</b> Required if connecting as SYSDBA (ORAMTS_CFLG_SYSDBALOGN).</li> <li>• <b>SYSOPER Login</b> Required if connecting as SYSOPER (ORAMTS_CFLG_SYSOPRLOGN).</li> <li>• <b>Preliminary INTERNAL Login</b> Required if connecting as INTERNAL (ORAMTS_CFLG_PRELIMAUTH).</li> </ul>

Default value	OraMTSConFlgs = 'ORAMTS_CFLG_ALLDEFAULT'
Usage	<p>If a transactional PowerBuilder component deployed to COM+ uses a PowerBuilder native interface to connect to an Oracle 8.1.5 or higher database, COM+ attempts to obtain a pooled connection and enlist the connection in a transaction. You can specify different behavior by selecting one or more of the available options.</p> <p>When the Oracle database interface is running under COM+, ThreadSafe mode is enabled by default and the value of the ThreadSafe parameter is ignored.</p> <p>This parameter cannot be set dynamically. The value set when the connection is made remains in effect until it is disconnected.</p> <p>These values are not mutually exclusive. They are chained using the pipe character in the parameter.</p>

---

#### Requirements for COM+ transactional support

Oracle Services for COM+ must be installed and configured.

---

Examples	<p>To obtain an enlisted connection using the INTERNAL account:</p> <ul style="list-style-type: none"><li>• <b>Database profile</b> Select the Preliminary INTERNAL Login check box on the EAServer/COM+ tab in the Database Profile Setup dialog box. The All Default check box is selected by default.</li><li>• <b>Application</b> Type the following in code (use   to signify a logical OR of the flags):</li></ul>
----------	--

```
SQLCA.DBParm = "OraMTSConFlgs =  
'ORAMTS_CFLG_ALLDEFAULT|ORAMTS_CFLG_PRELIMAUTH' "
```

## PackageProcs

Description	Specifies that the stored procedures and functions encapsulated in an Oracle database package should be appended to the lists of Oracle standalone stored procedures and functions displayed in the DataWindow and Database painters.
-------------	---

---

#### When to specify PackageProcs

You must specify the PackageProcs parameter *before* connecting to the database.

---

Applies to	O84 Oracle 8.x and Oracle8i O90 Oracle9i O10 Oracle 10g
------------	---



Syntax	<p><b>PackageProcs</b> = <i>value</i></p> <table border="1"> <thead> <tr> <th style="text-align: left;">Parameter</th> <th style="text-align: left;">Description</th> </tr> </thead> <tbody> <tr> <td><i>value</i></td> <td> <p>Specifies that package-stored procedures and functions should be appended to the lists of stored procedures and functions. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not append package-stored procedures and functions.</li> <li>• <b>1</b> Append package-stored procedures and functions.</li> </ul> </td> </tr> </tbody> </table>	Parameter	Description	<i>value</i>	<p>Specifies that package-stored procedures and functions should be appended to the lists of stored procedures and functions. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not append package-stored procedures and functions.</li> <li>• <b>1</b> Append package-stored procedures and functions.</li> </ul>
Parameter	Description				
<i>value</i>	<p>Specifies that package-stored procedures and functions should be appended to the lists of stored procedures and functions. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not append package-stored procedures and functions.</li> <li>• <b>1</b> Append package-stored procedures and functions.</li> </ul>				
Default value	PackageProcs = 0				
Usage	<p>A package is an encapsulated collection of related program objects (such as procedures, functions, variables, and cursors) stored together in an Oracle database. Listing the objects contained in a package might impose a performance penalty on your Oracle database connection. When displayed in the DataWindow painter, only those objects that contain a REF CURSOR or SELECT statement parameter are listed. When displayed in the Database painter, all objects are listed. The text source displayed is that of the entire package.</p>				
Examples	<p>To specify that you want Oracle package objects appended to the lists of stored procedures and functions:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Select the List Package Subprograms check box on the System tab in the Database Profile Setup dialog box.</li> <li>• <b>Application</b> Type the following in code:           <pre style="margin-left: 40px;">SQLCA.DBParm="PackageProcs=1"</pre> </li> </ul>				

## PacketSize (ODBC)

Description	<p>Specifies the network packet size in bytes when you access an ODBC data source in PowerBuilder.</p> <p>Many back-end DBMSs either do not support the PacketSize option or can return only the current network packet size. For information about whether the DBMS you are accessing supports PacketSize, see your DBMS documentation.</p> <hr/> <p><b>When to specify PacketSize</b>          If your back-end DBMS supports it, you must specify the PacketSize parameter <i>before</i> connecting to the database.</p> <hr/>
-------------	---

Applies to	ODBC (if ODBC 2.0 or higher driver and back-end DBMS support this feature)				
Syntax	<b>PacketSize</b> = <i>value</i> <table><thead><tr><th>Parameter</th><th>Description</th></tr></thead><tbody><tr><td><i>value</i></td><td>A 32-bit integer value that specifies the network packet size in bytes</td></tr></tbody></table>	Parameter	Description	<i>value</i>	A 32-bit integer value that specifies the network packet size in bytes
Parameter	Description				
<i>value</i>	A 32-bit integer value that specifies the network packet size in bytes				
Default value	The default value for PacketSize is the default for your back-end DBMS.				
Usage	If the PacketSize value you specify is larger than the maximum network packet size or smaller than the minimum network packet size, your ODBC driver substitutes the maximum or minimum value for the value you specified.				
Examples	To set the network packet size for an ODBC data source to 2048 bytes: <ul style="list-style-type: none"><li>• <b>Database profile</b> Type the following in the Packet Size box on the Network tab in the Database Profile Setup dialog box: <pre>2048</pre></li><li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm="PacketSize=2048"</pre></li></ul>				

## PacketSize (DIR, SYC)

Description	<p>When connecting to a database, specifies the packet size in bytes that you want the server to set for transferring data to and from your PowerBuilder application. A <b>packet</b> is a fixed-size chunk of data for sending information over a network.</p> <p>If the server has space limitations, it sets the packet size to less than the specified PacketSize value. Otherwise, it sets the size equal to the PacketSize value. The default value is 512 bytes.</p> <hr/> <p><b>When to specify PacketSize</b> You must specify the PacketSize parameter <i>before</i> connecting to the database.</p> <hr/>
Applies to	DIR Sybase DirectConnect SYC Sybase Adaptive Server Enterprise

## Syntax

**PacketSize** = *value*

Parameter	Description
<i>value</i>	A value specifying the packet size in bytes that a database server sets for transferring data to and from your application. The value must be a multiple of 512 bytes (default = 512 bytes).

## Default value

PacketSize = 512

## Usage

*When to set* If your PowerBuilder application sends or receives large amounts of text or image data from the server, setting the PacketSize value larger than the default 512 bytes might speed performance by causing fewer network read and write operations.

*Adaptive Server Enterprise and DirectConnect* Before setting PacketSize for use with an Adaptive Server Enterprise or DirectConnect database, you or your system administrator must set the following configuration variables on the server for PacketSize to take effect:

- **Additional netmem** Sets the maximum size of additional memory that can be used for network packets larger than the default size.
- **Maximum network packet size** Sets the maximum network packet size for all database users.

For instructions on setting these configuration variables, see your database documentation.

## Examples

To specify that the database server should set the packet size equal to or less than 2048 bytes:

- **Database profile** Type the following in the Packet Size box on the Network tab in the Database Profile Setup dialog box:

```
2048
```

- **Application** Type the following in code:

```
SQLCA.DBParm="PacketSize=2048"
```

## PBCatalogOwner

## Description

Specifies a nondefault owner for the extended attribute system tables. These five tables contain default extended attribute information for your database.

When you specify a PBCatalogOwner name that is different from the default owner for your DBMS, PowerBuilder creates a new set of tables with the owner name you specify.

**When to specify PBCatalogOwner**

You must specify the PBCatalogOwner parameter *before* connecting to the database.

Applies to

ADO.NET  
 DIR Sybase DirectConnect  
 JDB JDBC  
 ODBC  
 OLE DB  
 O84 Oracle 8.x and Oracle8i  
 O90 Oracle9i  
 O10 Oracle 10g  
 SYC and SYJ Sybase Adaptive Server Enterprise

Syntax

**PBCatalogOwner** = 'owner\_name'

Parameter	Description
owner_name	Specifies the owner of the extended attribute system tables. <b>For DB2 databases</b> If you use the DB2SYSPB.SQL script to create the extended attribute system tables in a DB2 database and replace all instances of PBOwner in the script with the name of a nondefault table owner, <i>owner_name</i> must be the same as the owner specified in the DB2SYSPB.SQL script.

Default value

The default value for PBCatalogOwner depends on the DBMS you are accessing, as follows:

DBMS	PBCatalogOwner default value
ADO.NET	If a value for PBCatalogOwner is not specified in the database profile or in the registry, the default value is the user ID specified in the database profile.
JDBC	If a value for PBCatalogOwner is not specified in the database profile or in the registry, the default value is the user ID specified in the database profile.
ODBC	If a value for PBCatalogOwner is not specified in the database profile or in the PBODBn0 initialization file, the default value is the user ID specified in the database profile.
OLE DB	If a value for PBCatalogOwner is not specified in the database profile or in the registry, the default value is the user ID specified in the database profile.
Oracle	PBCatalogOwner = 'SYSTEM'

DBMS	PBCatalogOwner default value
Sybase Adaptive Server Enterprise	PBCatalogOwner = 'dbo'
Sybase DirectConnect	PBCatalogOwner = 'sqlca.logid'

**Usage**

*When to set* When you specify a nondefault owner for the extended attribute system tables, you are in effect creating alternative tables. This is useful if you want to test new validation rules or display formats without overwriting the extended attributes currently in the default tables.

*JDBC databases* When you connect to a JDBC database and a value for PBCatalogOwner is set in both the database profile and the registry, the setting in the profile overrides the setting in the registry.

*ODBC data sources* When you connect to an ODBC data source and a value for PBCatalogOwner is set in both the database profile and the PBODB105 initialization file, the setting in the profile overrides the setting in the PBODB105 initialization file.

*DB2 databases* When you connect to a DB2 database, you can use the DB2SYSPB.SQL script to create the extended attribute system tables. If you use the DB2SYSPB.SQL script, keep the following in mind:

- You can edit the script to change all instances of PBOwner to another name, or leave the table owner as PBOwner in the script (the default).

**Specifying SYSIBM is prohibited**

DB2 prohibits you from specifying SYSIBM as the table owner.

- You can set the PBCatalogOwner parameter to the owner you specified in this script or to PBOwner if you did not edit the script.

This parameter cannot be set dynamically. The value set when the connection is made remains in effect until it is disconnected.

**Examples**

This example shows how to create a new set of extended attribute system tables with the owner TEST. The names of the new tables have the prefix TEST, such as TEST.pbcatcol, TEST.pbcatcdt, and so on.

- **Database profile** Type the following in the PB Catalog Table Owner box on the System tab in the Database Profile Setup dialog box:

```
TEST
```

- **Application** Type the following in code:

```
SQLCA.DBParm="PBCatalogOwner='TEST' "
```

## PBMaxBlobSize

Description Specifies the maximum blob size that PowerBuilder can read into memory.

---

### When to specify PBMaxBlobSize

You must specify a value for the PBMaxBlobSize parameter *before* connecting to the database.

---

Applies to ADO.NET  
OLE DB

Syntax **PBMaxBlobSize** = *value*

Default value PBMaxBlobSize=1024000 (ADO.NET and OLE DB),  
PBMaxBlobSize=32767 (other interfaces)

Usage PowerBuilder does not restrict the maximum blob size. Instead, the maximum blob size is determined by the machine on which the application is running. If the blob size exceeds the available memory on the machine on which the application is running, PowerBuilder reads the blob in chunks if the data provider supports the ISequentialStream interface. If the blob size exceeds the default value and the data provider does not support the ISequentialStream interface, PowerBuilder truncates it and reports an out-of-memory error. Use the PBMaxBlobSize parameter to specify larger maximum blob sizes.

Examples To set the PBMaxBlobSize value to 200000:

- **Database profile** Type the following in the Maximum In-Memory Blob Size box on the Transaction tab in the Database Profile Setup dialog box:

```
200000
```

- **Application** Type the following in code:

```
SQLCA.DBParm="PBMaxBlobSize=200000"
```

## PBNewSPInvocation

Description Uses an alternative method to invoke a stored procedure.

Applies to ODBC

Syntax **PBNewSPInvocation = 'value'**

Parameter	Description
<i>value</i>	<p>Specifies whether the standard method or an alternative method is used to invoke a stored procedure. Values are:</p> <ul style="list-style-type: none"> <li>• <b>No</b> (Default) Use the standard method to invoke a stored procedure.</li> <li>• <b>Yes</b> Use the alternative method to invoke a stored procedure.</li> </ul>

Default value PBNewSPInvocation = 'No'

Usage Output parameters might not be returned when you use an embedded SQL command to call a stored procedure. You can set PBNewSPInvocation to 'Yes' to use an alternative method to invoke a stored procedure. The behavior of the PowerBuilder ODBC driver when this parameter is set is consistent with the default behavior of the OLE DB and JDBC drivers.

If PBNewSPInvocation is set to 'Yes', the alternative method is used when you retrieve data into a DataWindow object that uses a stored procedure. This parameter has no effect when you use RPC to invoke a stored procedure.

When PBNewSPInvocation is set to 'Yes', the values of the PBUseProcOwner and CallEscape parameters are ignored.

Examples To set the parameter for all connections, add the following line to every relevant section (such as ;IBM DB2/NT 2.1 DB2CLI for a DB2 connection on Windows) in your *pbodb105.ini* file:

```
PBNewSPInvocation='Yes'
```

For more information about editing *pbodb105.ini*, see the Appendix in *Connecting to Your Database*.

You can also set the parameter at runtime. For example:

```
SQLCA.DBParm="PBNewSPInvocation='Yes' "
```

The value that is set at runtime overrides the value in the *pbodb105.ini* file.

To obtain the value of the stored procedure's output parameter, use the OUTPUT or OUT keyword. For example:

```
DECLARE sp_test PROCEDURE FOR SP1 VAR0=:ARGIN,  
VAR1=:ARGOUT OUTPUT USING SQLCA;
```

If the stored procedure contains result sets, you must fetch the result sets first. If the stored procedure has a return value and you want to obtain it, use the format `RC=SP1`:

```
DECLARE sp_test PROCEDURE FOR RC=SP1 VAR0=:ARGIN,
VAR1=:ARGOUT OUTPUT USING SQLCA;
```

See also `DefaultProcOwner`

## PBTrimCharColumns

**Description** Specifies whether PowerBuilder should trim trailing spaces from data values retrieved from the following datatypes: Char, Char for Bit Data, VarChar, and VarChar for Bit Data.

**Applies to** ODBC  
OLE DB

**Syntax** `PBTrimCharColumns = value`

Parameter	Description
<i>value</i>	Specifies whether PowerBuilder should trim trailing spaces from data of type Char, Char for Bit Data, and VarChar for Bit Data. Values are: <ul style="list-style-type: none"> <li><b>NO</b> (Default) Do not trim trailing spaces.</li> <li><b>YES</b> Trim trailing spaces.</li> </ul>

**Default value** 'NO'

**Usage** This parameter can only be set in the *pbodb105.ini* file. For ODBC, you can set the TrimSpaces parameter in the Database Profile Setup dialog box or in code to perform the same function.

By default, PowerBuilder trims spaces from the following datatypes: Char, Char for Bit Data, VarChar, and VarChar for Bit Data.

If your DBMS makes a distinction between Char data with trailing spaces and Char data without trailing spaces when evaluating a WHERE clause expression, you might receive the message `Row changed between retrieve and update` when your DataWindow update properties are set to “Key and updateable columns.” To prevent this, change your DataWindow update properties. In embedded SQL, you can check `Sqlca.Sqlnrows` after each update to determine if the update took place. Avoid using Char data columns in the WHERE clause of an UPDATE or DELETE statement when `PBTrimCharColumns='YES'`.



**Examples** To specify that PowerBuilder should trim trailing spaces, add the following line to the section for the database you are accessing:

```
PBTrimCharColumns='YES'
```

**See also** TrimSpaces

## PBUseProcOwner

**Description** When you access a database through the ODBC interface and define a DataWindow object that uses a stored procedure as its data source, PBUseProcOwner specifies whether PowerBuilder should qualify the stored procedure with the owner name in the SQL EXECUTE statement passed to the driver.

PowerBuilder qualifies the stored procedure with an owner only if the owner associated with the stored procedure is different from the ID of the current user (the developer building the DataWindow object or the user running the application containing the DataWindow object).

**Applies to** ODBC

**Syntax** **PBUseProcOwner** = 'value'

Parameter	Description
<i>value</i>	<p>Specifies whether PowerBuilder should qualify the stored procedure with its owner name in the SQL EXECUTE statement built by the DataWindow object and passed to the driver. Values are:</p> <ul style="list-style-type: none"> <li> <b>Yes</b> If the owner associated with the stored procedure is different from the current user ID, PowerBuilder qualifies the stored procedure with its owner name in the SQL EXECUTE statement and passes this information to the driver. This allows users to execute stored procedures they do not own. For example: <pre>EXECUTE FRAN.MYPROCEDURE</pre> </li> <li> <b>No</b> (Default) PowerBuilder does not qualify the stored procedure with its owner name in the SQL EXECUTE statement passed to the driver. For example: <pre>EXECUTE MYPROCEDURE</pre> </li> </ul>

**Default value** PBUseProcOwner = 'No'

## Usage

*Determining the PBUseProcOwner value* PowerBuilder searches the following in this order to determine the PBUseProcOwner value:

- 1 The section for your database profile in the PowerBuilder initialization file (in the development environment) or the value of the transaction object's DBParm property (in an application).
- 2 The section for your ODBC driver in the *PBODBI05* initialization file.

If PowerBuilder does not find a PBUseProcOwner value in these locations, it defaults to a value of 'No'.

*If DBA owns the Adaptive Server Anywhere stored procedure* DBA (database administrator) is a reserved word in Adaptive Server Anywhere syntax.

If you define a DataWindow object with an Adaptive Server Anywhere stored procedure as its data source and DBA owns the stored procedure, the painter passes the following SQL EXECUTE statement to the ODBC driver if PBUseProcOwner is set to Yes:

```
EXECUTE DBA.MYPROCEDURE
```

This statement generates a syntax error because it includes the DBA reserved word.

If DBA owns the Adaptive Server Anywhere stored procedure you are using, you can avoid this syntax error by setting PBUseProcOwner to No so that PowerBuilder does not qualify the stored procedure with DBA.

In some situations, however, you *must* qualify the stored procedure with the DBA owner. For example, the DBA might want to grant execute permission to another user ID. In this case, you can avoid errors by editing the SQL EXECUTE syntax to enclose DBA in quotes, like this:

```
EXECUTE "DBA".MYPROCEDURE
```

## Examples

To specify that PowerBuilder should qualify the stored procedure with its owner name in the SQL EXECUTE statement:

- **Database profile** Select the Qualify Stored Procedures With Owner Name check box on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="PBUseProcOwner='Yes' "
```

## PersistEncrypted

**Description** Specifies whether the data source you are accessing through the OLE DB interface is allowed to save your encrypted password.

---

### When to specify PersistEncrypted

You must specify the PersistEncrypted parameter *before* connecting to the database.

---

**Applies to** OLE DB

**Syntax** `PersistEncrypted = 'value'`

Parameter	Description
<i>value</i>	Specifies whether the data source can save your encrypted password. Values are: <ul style="list-style-type: none"> <li>• <b>True</b> Tells the data source it can save your password.</li> <li>• <b>False</b> (Default) Tells the data source it cannot save your password.</li> </ul>

**Default value** `PersistEncrypted = 'False'`

**Examples** To tell the data source you are accessing through OLE DB that it can save your password:

- **Database profile** Select the Persist Encrypted check box on the Security tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="PersistEncrypted='True' "
```

**See also** DataLink  
MaskPassword  
EncryptPassword  
PersistSensitive

## PersistSensitive

**Description** Specifies whether the data source you are accessing through the OLE DB interface is allowed to save sensitive authentication information, such as a password, along with other authentication information.

---

### When to specify PersistSensitive

You must specify the PersistSensitive parameter *before* connecting to the database.

---

**Applies to** OLE DB

**Syntax** `PersistSensitive = 'value'`

Parameter	Description
<i>value</i>	Specifies whether the data source can save your authentication information. Values are: <ul style="list-style-type: none"><li>• <b>True</b> Tells the data source it can save your authentication information.</li><li>• <b>False</b> (Default) Tells the data source it cannot save your authentication information.</li></ul>

**Default value** PersistSensitive = 'False'

**Examples** To tell the data source you are accessing through OLE DB that it can save your authentication information:

- **Database profile** Select the Persist Security Info check box on the Security tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="PersistSensitive='True' "
```

**See also** MaskPassword  
EncryptPassword  
PersistEncrypted

## Properties

Description	Sets properties specific to the particular JDBC driver you are using to connect to the database.
Applies to	JDB JDBC
Syntax	<b>Properties</b> = ' <i>property_value</i> '
Default value	None
Usage	The Driver-Specific Properties box allows you to set properties specific to a particular driver.  For information about the properties supported by your JDBC driver, see the vendor's documentation.

---

### Define User ID and Password

If properties are defined, you *must* also define the user ID and password in the properties box.

---

Examples	<p>To set a property for the Sybase jConnect driver:</p> <ul style="list-style-type: none"> <li> <b>Database profile</b> Type the following in the Driver-Specify Properties box on the Connection tab in the Database Profile Setup dialog box:           <pre>SQLINITSTRING=set TextSize 32000; user=sa;password=manager</pre> </li> <li> <b>Application</b> Type the following in code:           <pre>SQLCA.DBParm = "Properties = 'SQLINITSTRING=set TextSize 32000;user=sa;password=manager' "</pre> </li> </ul>
See also	<p>Driver URL</p>

## ProtectionLevel

**Description** Specifies the level of protection applied to data sent between PowerBuilder and the data server through the OLE DB data provider. This parameter applies only to network connections other than Remote Procedure Call (RPC) connections. Similar levels of protection can be specified for authenticated RPC connections.

---

### When to specify ProtectionLevel

You must specify the ProtectionLevel parameter *before* connecting to the database.

---

**Applies to** OLE DB

**Syntax** ProtectionLevel = 'value'

Parameter	Description
<i>value</i>	<p>Specifies the level of protection applied to data sent between PowerBuilder and the data server. Values are:</p> <ul style="list-style-type: none"><li>• <b>Not set</b> No level of protection is selected.</li><li>• <b>Call</b> Authenticates the source of the data at the beginning of each request from the client to the server.</li><li>• <b>Connect</b> Authenticates only when the client establishes the connection with the server.</li><li>• <b>None</b> Performs no authentication of data.</li><li>• <b>Packet</b> Authenticates that all data received is from the client.</li><li>• <b>Packet (Integrity)</b> Authenticates that all data received is from the client and that it has not been changed in transit.</li><li>• <b>Packet (Privacy)</b> Authenticates that all data received is from the client, that it has not been changed in transit, and that it protects the privacy of the data by encrypting it.</li></ul>

**Default value** Not set

**Examples** To set a level of protection for the data sent between PowerBuilder and the data server:

- **Database profile** On the Security tab in the Database Profile Setup dialog box, select Connect from the Protection Level drop-down list.
- **Application** Type the following in code:

```
SQLCA.DBParm=  
"PROTECTIONLEVEL='DB_PROT_LEVEL_CONNECT' "
```

**See also** DataLink

## Provider

Description Identifies the data provider you want to use to connect to your data source.

---

### When to specify Provider

You must specify the Provider parameter *before* connecting to the database.

---

Applies to	ADO.NET OLE DB
Syntax	<b>Provider</b> = ' <i>provider_name</i> '
Default value	None
Usage	<p>Select a data provider from the list of installed data providers displayed in the Provider drop-down list. For example, if you are using Microsoft's OLE DB Provider for ODBC, select MSDASQL as the Provider value. If you are using Microsoft's OLE DB Provider for SQL Server, select SQLOLEDB as the Provider value.</p> <p>For more information, see the documentation provided by your OLE DB or ADO.NET data provider.</p>
Examples	<p><b>Example 1</b> To use the Microsoft OLE DB Provider for ODBC to connect to the EAS Demo DB:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Select MSDASQL from the Provider drop-down list on the Connection tab in the Database Profile Setup dialog box for OLE DB.</li> <li>• <b>Application</b> Type the following in code:           <pre>SQLCA.DBParm="Provider='MSDASQL' "</pre> </li> </ul> <p><b>Example 2</b> To use the Microsoft OLE DB Provider for Oracle to connect to an Oracle 8 database:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Select MSDAORA from the Provider drop-down list on the Connection tab in the Database Profile Setup dialog box.</li> <li>• <b>Application</b> Type the following in code:           <pre>SQLCA.DBParm="Provider='MSDAORA' "</pre> </li> </ul> <p><b>Example 3</b> To use the Sybase Oracle8 ADO Provider to connect to an Oracle 8 database:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Select Sybase.Oracle8ADOPROvider from the Provider drop-down list on the Connection tab in the Database Profile Setup dialog box for ADO.NET.</li> </ul>

- **Application** Type the following in code:

```
SQLCA.DBParm =  
"PROVIDER='Sybase.Oracle8ADOProvider' "
```

See also

DataLink  
DataSource

## ProviderString

Description

When connecting to a Microsoft SQL Server database, identifies the specific database on the server to which you want to connect.

---

### When to specify ProviderString

You must specify the ProviderString parameter *before* connecting to the database.

---

Applies to

ADO.NET  
OLE DB

Syntax

**ProviderString** = 'value'

Default value

None

Usage

Since Microsoft SQL Server supports multiple instances of a database on a single server, you must identify the specific database to which you want to connect by entering the database name.

For more information, see the documentation for Microsoft SQL Server.

Examples

To identify a specific Microsoft SQL Server database:

- **Database profile** Enter the following in the Extended Properties box on the Connection tab in the Database Profile Setup dialog box for OLE DB, or in the Driver-Specific Parameters box for ADO.NET:

```
Database = demodb1
```

- **Application** Type the following in code:

```
SQLCA.DBParm="ProviderString='database=demodb1' "
```

See also

URL



## ProxyUserName

**Description** Specifies that you want EAServer to retrieve a connection from a connection cache by proxy.

This parameter applies *only* when a PowerBuilder custom class user object is deployed as an EAServer component.

**Applies to** JDB JDBC  
ODBC  
SYJ Sybase Adaptive Server Enterprise

**Syntax** ProxyUserName = 'value'

Parameter	Description
value	Specifies the alternate login name that can use a connection.

**Default value** None

**Usage** Regardless of whether you access a cache by user or name, you can retrieve a connection by proxy. Retrieving a connection by proxy means that you can assume the identity and privileges of another user by providing an alternative login name.

This feature can be used with any database that recognizes the SQL command **set session authorization**. In order for user A to use the ProxyUserName parameter to assume the identity of another user B, user A must have permission to execute this statement. For example, for Adaptive Server Anywhere, user A must have DBA authority, and for Adaptive Server Enterprise, user A must have been granted permission to execute **set session authorization** by a System Security Officer.

---

### Using the SYJ interface

Sybase EAServer uses a slightly different version of the CT-Lib software. Therefore, *at runtime*, you need to use the SYJ database interface rather than SYC to connect to an Adaptive Server Enterprise database. The SYJ Database Profile Setup dialog box provides a convenient way to set the appropriate connection parameters and then copy the syntax from the Preview tab into the script for your Transaction object.

You cannot use the SYJ interface, however, to connect to the database in the PowerBuilder development environment. Therefore, *during the development phase* (before the component has been deployed to EAServer), you must use SYC to connect to the database.

---

For information on how to use PowerBuilder to build EAServer components and enable set-proxy support, see *Application Techniques*.

Examples

On the EAServer tab in the Database Profile Setup dialog box, enter the alternative login name in the Proxy User Name box. The PowerScript syntax for the ProxyUserName parameter displays on the Preview tab:

```
SQLCA.DBParm = "ProxyUserName = 'pikachu'"
```

Copy the syntax from the Preview tab into your script.

See also

CacheName

## PWDialog

Description

Controls whether a Password Expired dialog box displays in an application at runtime if a user's password has expired.

When PWDialog is set to 1, the Password Expired dialog box prompts users to change their passwords if they attempt to log in to the database with an expired password. By default, PWDialog is set to 0 to specify that the Password Expired dialog box does not display in your application at runtime.

The setting of PWDialog affects applications only at runtime. It has no effect in the development environment because, regardless of the PWDialog setting, the Change Password dialog box displays in the development environment to prompt users to change an expired password.

---

### When to specify PWDialog

You must specify a value for PWDialog *before* connecting to the database.

---

Applies to

O84 Oracle 8.x and Oracle8i  
 O90 Oracle9i  
 O10 Oracle 10g  
 SYC Sybase Adaptive Server Enterprise

Syntax

**PWDialog** = *value*

Parameter	Description
<i>value</i>	<p>Specifies whether the Password Expired dialog box displays in an application at execution time to prompt the user to change an expired login password. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not display the Password Expired dialog box at execution time.</li> <li>• <b>1</b> Display the Password Expired dialog box at execution time to prompt the user to change an expired password.</li> </ul>

Default value	PWDIALOG = 0
Usage	<p><i>When to use</i> Setting PWDIALOG to 1 to display the Password Expired dialog box in your application provides a convenient way for you to notify your users that a password has expired and allow them to change it.</p> <p><i>What happens</i> When the Password Expired dialog box displays in your application at runtime, it notifies users that the password for their login ID has expired and prompts them to supply a new password. For example, for Adaptive Server Enterprise, the sp_password system stored procedure runs to set the new password. Once the password has been changed, the database connection succeeds.</p> <p>If the user clicks Cancel to close the Password Expired dialog box without changing the password, the database connection fails and a message displays indicating that the password has expired.</p>
Examples	<p>To display the Password Expired dialog box when needed in your application:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Although the setting of PWDIALOG has no effect in the development environment, you might want to set it in your database profile to generate connection syntax on the Preview tab that you can copy into your code. Select the Display Runtime Dialog When Password Expires check box (for SYC connections) or the Password Expiration Dialog check box (for Oracle connections) on the Connection tab in the Database Profile Setup dialog box.</li> <li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm="PWDIALOG=1"</pre> </li> </ul>

## PWEncrypt

Description	PWEncrypt specifies whether you want Open Client to automatically encrypt your password when connecting to a Sybase Adaptive Server Enterprise database in PowerBuilder.
-------------	--

---

### When to specify PWEncrypt

You must specify the PWEncrypt parameter *before* connecting to the database.

---

Applies to	SYC Sybase Adaptive Server Enterprise
------------	---------------------------------------

Syntax

**PWEncrypt** = 'value'

Parameter	Description
<i>value</i>	Specifies whether you want the Open Client software to encrypt your password. Values are: <ul style="list-style-type: none"> <li>• <b>Yes</b> (Default) Tells Open Client to encrypt the password by setting the CS_SEC_ENCRYPTION connection property to CS_TRUE.</li> <li>• <b>No</b> Tells Open Client not to encrypt the password by setting the CS_SEC_ENCRYPTION connection property to CS_FALSE.</li> </ul>

Default value

PWEncrypt = 'Yes'

Examples

To tell Open Client not to encrypt your password when connecting to a Sybase Adaptive Server Enterprise database in PowerBuilder:

- **Database profile** Clear the Encrypt Password check box on the Network tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "PWEncrypt='No' "
```

## PWExpDialog

Description

Controls whether an informational dialog box displays in an application at runtime if a user's password is about to expire.

When PWExpDialog is set to 1, a dialog box displays advising users that their passwords will expire in a given number of days. By default, PWExpDialog is set to 0 to specify that the dialog box does not display in your application at runtime.

---

### When to specify PWExpDialog

You must specify a value for PWExpDialog *before* connecting to the database.

---

Applies to

O84 Oracle 8.x and Oracle8i  
O90 Oracle9i  
SYC Sybase Adaptive Server Enterprise

Syntax	<b>PWExpDialog = value</b>				
	<table border="1"> <thead> <tr> <th>Parameter</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><i>value</i></td> <td> <p>Specifies whether an informational dialog box displays in an application at runtime to advise the user that a login password will expire in a given number of days. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not display the dialog box at runtime.</li> <li>• <b>1</b> Display the dialog box at runtime.</li> </ul> </td> </tr> </tbody> </table>	Parameter	Description	<i>value</i>	<p>Specifies whether an informational dialog box displays in an application at runtime to advise the user that a login password will expire in a given number of days. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not display the dialog box at runtime.</li> <li>• <b>1</b> Display the dialog box at runtime.</li> </ul>
Parameter	Description				
<i>value</i>	<p>Specifies whether an informational dialog box displays in an application at runtime to advise the user that a login password will expire in a given number of days. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not display the dialog box at runtime.</li> <li>• <b>1</b> Display the dialog box at runtime.</li> </ul>				
Default value	PWExpDialog = 0				
Usage	When this parameter is set to 1, the Oracle ORA-28002 and ORA-28011 and the Adaptive Server 4023 informational messages display.				
Examples	<p>To display the dialog box when needed in your application, type the following in code:</p> <pre>SQLCA.DBParm = "PWExpDialog=1"</pre>				

## QualifyPublic

Description	Specifies that the PUBLIC qualifier prepended to Oracle synonyms belonging to the public schema or user group is retained in the SQL Select table list.				
	<hr/> <p><b>When to specify QualifyPublic</b> You must specify the QualifyPublic parameter <i>before</i> connecting to the database.</p> <hr/>				
Applies to	<p>O84 Oracle 8.x and Oracle8i  O90 Oracle9i  O10 Oracle 10g</p>				
Syntax	<b>QualifyPublic = value</b>				
	<table border="1"> <thead> <tr> <th>Parameter</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><i>value</i></td> <td> <p>Specifies that the PUBLIC qualifier should be retained in the SQL Select table list. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not retain the PUBLIC qualifier.</li> <li>• <b>1</b> Do retain the PUBLIC qualifier.</li> </ul> </td> </tr> </tbody> </table>	Parameter	Description	<i>value</i>	<p>Specifies that the PUBLIC qualifier should be retained in the SQL Select table list. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not retain the PUBLIC qualifier.</li> <li>• <b>1</b> Do retain the PUBLIC qualifier.</li> </ul>
Parameter	Description				
<i>value</i>	<p>Specifies that the PUBLIC qualifier should be retained in the SQL Select table list. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not retain the PUBLIC qualifier.</li> <li>• <b>1</b> Do retain the PUBLIC qualifier.</li> </ul>				
Default value	QualifyPublic = 0				

**Usage** PowerBuilder's default behavior has been to discard the PUBLIC qualifier so that the object reference is generalized in the generated SQL statement, facilitating the deployment of an application from a development database instance to a production database. However, in certain DataWindow objects, the absence of the PUBLIC qualifier breaks the association of the synonym with its extended attributes, preventing these attributes from being used. The QualifyPublic parameter allows you to specify whether the PUBLIC qualifier should be retained.

**Examples** To specify that you want the PUBLIC qualifier to be retained in the SQL Select table list:

- **Database profile** Select the Qualify Public Synonyms check box on the System tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "QualifyPublic=1"
```

## Release

**Description** Specifies what version of Sybase Open Client Client-Library (CT-Lib) software is in use on the client workstation.

---

### When to specify Release

You must specify a value for Release *before* connecting to the database.

---

**Applies to** SYC Sybase Adaptive Server Enterprise

**Syntax** `Release = 'value'`

Parameter	Description
<i>value</i>	<p>Specifies the version of Open Client Client-Library your application uses.</p> <p>The value corresponds to the value of the CS_VERSION property that is used to allocate a context structure for the client. Multiple values that specify the same client context are provided for backwards compatibility. Values are:</p> <ul style="list-style-type: none"> <li>• <b>10.x</b> CS_VERSION_100</li> <li>• <b>11</b> CS_VERSION_110</li> <li>• <b>11.5</b> CS_VERSION_110</li> <li>• <b>12</b> CS_VERSION_110</li> <li>• <b>12.5</b> CS_VERSION_125</li> <li>• <b>12.5.1</b> CS_VERSION_125</li> <li>• <b>15</b> CS_VERSION_15</li> </ul>

Default value	Release='11'
Usage	<p>The Release parameter must correspond to the version of Open Client software installed on the client workstation. For example, do not specify 12.5 or 12.5.1 if your Open Client version is 12.0, even if your Adaptive Server version is 12.5 or 12.5.1.</p> <p>To use Adaptive Server 15, you must install Open Client version 15 on the client computer and set the Release parameter to 15 to establish an Open Client 15 client context.</p> <p>The Open Client context is allocated by the first <i>PBSYC105.DLL</i> database connection. This context acts as the parent context for all subsequent <i>PBSYC105.DLL</i> connections. Therefore, you must specify the same value for the Release parameter for all your connections.</p> <p>The SYC driver links to the appropriate version of the client libraries dynamically and the Open Client context is released when all connections are closed. If you open multiple connections, the first Open Client context established is used for all of them. If you need to establish a new Open Client context in the development environment, close all open connections and establish a new connection with the Release parameter set to the context you require.</p> <p>During each database login, <i>PBSYC105.DLL</i> automatically determines the version of Adaptive Server being accessed. It customizes its behavior to optimize performance and features for the combination of the Adaptive Server version and the Open Client context specified in the Release parameter. Specifying a value for Release that does not correspond to the Open Client software on the client can cause unpredictable results.</p> <p>The values 12.5 and 12.5.1 both open an Open Client 12.5 context. However, you should always specify Release='12.5' if you are using Open Client 12.5 and Release='12.5.1' if you are using Open Client 12.5.1. This ensures that <i>PBSYC105.DLL</i> correctly handles the following scenarios that require Open Client 12.5.1 and Adaptive Server 12.5.1:</p> <ul style="list-style-type: none"><li>• Use the Date and Time datatypes introduced in Adaptive Server 12.5.1 in RPC calls that explicitly call for these datatypes in the stored procedure argument list.</li><li>• Use the Date and Time datatypes in Update where current of and Delete where current of statements.</li></ul>

DataWindow retrieval, insert, update, and delete processing work correctly against Date and Time datatypes using any Open Client software and Adaptive Server 12.5.1. In the Database painter, the Date and Time datatypes display in the list of metadata types when you are connected to an Adaptive Server 12.5.1 server in any Open Client context.

Certain other features are supported only when you access a specified version of a SQL Server 10/11 or Adaptive Server Enterprise database using its associated Open Client software. For example, you must:

- Set the Release parameter to 11 or higher and use Open Client 11.x or higher and Adaptive Server 11.x or higher to take advantage of network-based security and directory services in your application.
- Set Release to 12.5 and use Open Client 12.5 or higher and Adaptive Server 12.5 or higher to access Char and VarChar columns with more than 255 characters.
- Set Release to 15 and use Open Client 15 or higher and Adaptive Server 15 or higher to access the UniText and 64-bit integer (BigInt) SQL datatypes added in version 15 of Adaptive Server.

#### Examples

To specify that your PowerBuilder application accesses an Adaptive Server Enterprise 15 database using an Open Client Client-Library 15 context:

- **Database profile** Select 15 from the Release drop-down list on the Connection tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm="Release='15' "
```

## ReleaseConnectionOption

Description	Specifies how EAServer should behave when it releases control of a connection. This parameter applies <i>only</i> when a PowerBuilder custom class user object is deployed as an EAServer component.
Applies to	JDB JDBC ODBC O84 Oracle 8.x and Oracle8i O90 Oracle9i O10 Oracle 10g SYJ Sybase Adaptive Server Enterprise
Syntax	<b>ReleaseConnectionOption</b> = 'value'



Parameter	Description
<i>value</i>	<p>Specifies how EAServer should behave when it releases control of a connection. Values are:</p> <ul style="list-style-type: none"> <li>• <b>JAG_CM_UNUSED</b> (Default) A connection taken from a cache is placed back in the cache and a connection created outside of a cache is closed and destroyed.</li> <li>• <b>JAG_CM_DROP</b> The connection is forced to close and is deallocated. If the connection came from a cache, a new connection is created in its place.</li> </ul>

Default value

ReleaseConnectionOption = 'JAG\_CM\_UNUSED'

Usage

Use JAG\_CM\_DROP to destroy a connection when errors have made it unusable. This parameter cannot be set dynamically. The value set when the connection is made remains in effect until it is disconnected.

---

### Using the SYJ interface

Sybase EAServer uses a slightly different version of the CT-Lib software. Therefore, *at runtime*, you need to use the SYJ database interface rather than SYC to connect to an Adaptive Server Enterprise database. The SYJ Database Profile Setup dialog box provides a convenient way to set the appropriate connection parameters and then copy the syntax from the Preview tab into the script for your Transaction object.

You cannot use the SYJ interface, however, to connect to the database in the PowerBuilder development environment. Therefore, *during the development phase* (before the component has been deployed to EAServer), you must use SYC to connect to the database.

---

For information on how to use PowerBuilder to build EAServer components, see *Application Techniques*.

Examples

On the EAServer tab in the Database Profile Setup dialog box, select JAG\_CM\_DROP from the Release Connection Option drop-down list. The PowerScript syntax for the ReleaseConnectionOption parameter displays on the Preview tab:

```
SQLCA.DBParm = "ReleaseConnectionOption =
'JAG_CM_DROP' "
```

Copy the syntax from the Preview tab into your script.

See also

CacheName  
GetConnectionOption  
UseContextObject

## Request

**Description** Specifies whether to allocate new transaction resources each time the client application sends a request and then release those resources after each request.

**Applies to** DIR Sybase DirectConnect (applies only to Access Service for DB2/MVS)

**Syntax** **Request = value**

Parameter	Description
<i>value</i>	Specifies whether you want to release transaction resources after each request. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Maintain resources for the duration of the database connection.</li> <li>• <b>1</b> Release resources after each request.</li> </ul>

**Default value** Request = 0

**Usage** *Requirements for using the Request parameter* Setting the Request parameter to 1 to release resources has an effect only when you do both of the following:

- Set the AutoCommit database preference to True to specify that PowerBuilder should issue SQL statements outside the scope of a transaction. (See the description of AutoCommit.)
- Specify the value for Request *before* connecting to a database.

*What happens* When you set the Request parameter to 1, transaction resources are allocated for each request and released when the request finishes. This might slow the performance of your application, but it allows more simultaneous users of the system.

**Examples** To specify that you want to release resources after each request:

- **Database profile** Select the Release Transaction Resources After Each Request check box on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Request=1"
```

**See also** AutoCommit

## RPCRebind

**Description** Specifies whether you want PowerBuilder to rebind Remote Procedure Call (RPC) parameters.

---

### When to specify RPCRebind

If your back-end DBMS supports it, you must specify the RPCRebind parameter *before* connecting to the database.

---

**Applies to** ODBC

**Syntax** `RPCRebind = value`

Parameter	Description
<i>value</i>	<p>Specifies whether you want PowerBuilder to rebind RPC parameters. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Use the bound variable to determine all required binding information.</li> <li>• <b>1</b> Rebind the parameters and use the parameter information returned from the database to bind the parameter.</li> </ul>

**Default value** `RPCRebind = 0`

**Usage** For those DBMSs that support RPC calls, PowerBuilder binds the parameters for the call based on the size of the variables bound to the parameters.

Some drivers require rebinding of the parameters so the parameter size (as returned from the back-end database) is used instead of the variable size. Failure to do this might result in an error or truncation for string parameters. However, some drivers always expect the binding to reflect the variable size. The RPCRebind parameter allows you to specify whether you want to rebind the parameters when RPCs are executed.

**Examples** To specify that PowerBuilder should rebind RPC parameters:

- **Database profile** Select the RPC Rebind check box on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "RPCRebind=1"
```

## ReturnCommandHandle

**Description** Specifies whether you want PowerBuilder to return a handle to a session object or a data source object when you call the DBHandle function.

**Applies to** OLE DB

**Syntax** ReturnCommandHandle = *value*

Parameter	Description
<i>value</i>	Specifies whether you want PowerBuilder to return a handle to a session object or a data source object. Values are: <ul style="list-style-type: none"><li>• <b>0</b> (Default) Return a data source object pointer.</li><li>• <b>1</b> Return a session object pointer.</li></ul>

**Default value** ReturnCommandHandle = 0

**Usage** DBHandle takes a transaction object as a parameter and returns a long variable that is an interface pointer to a data source object or a session object. By default the OLE DB interface returns the handle of a data source object. If ReturnCommandHandle is set to 1, the OLE DB interface returns the handle of a session object. This handle can then be passed to an external program and instantiated for use in enlisting the connection in a Microsoft DTC (Distributed Transaction Coordinator) transaction.

**Examples** For an example, see “DBHandle, OLE DB example” in the online Help.

## Scroll

**Description** Specifies whether you want to use a scroll cursor when connecting to an Informix database in PowerBuilder. When you fetch rows in an Informix table, using a scroll cursor enables you to fetch the next row, previous row, first row, or last row.

By default, PowerBuilder does not use scroll cursors in an Informix database connection.

**Applies to** IN9 Informix

**Syntax** **Scroll** = *value*

Parameter	Description
<i>value</i>	Specifies whether you want to use a scroll cursor when connecting to an Informix database in PowerBuilder. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not use a scroll cursor.</li> <li>• <b>1</b> Use a scroll cursor.</li> </ul>

Default value

Scroll = 0

Examples

To specify that you want to use a scroll cursor when connecting to an Informix database in PowerBuilder:

- **Database profile** Select the Use A Scroll Cursor check box on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Scroll=1"
```

## Sec\_Channel\_Bind

Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, `Sec_Channel_Bind` is one of several parameters that support login authentication for network-based security services. (For other login authentication parameters, see the See Also section.)

`Sec_Channel_Bind` controls whether your connection's security mechanism performs channel binding. When `Sec_Channel_Bind` is set to 1, both Sybase Open Client Client-Library (CT-Lib) and the server provide a network channel identifier to the security mechanism before connecting. The channel identifier contains the network addresses of the client and server.

When `Sec_Channel_Bind` is set to 0 (the default), no channel binding is performed.

You must specify a value for `Sec_Channel_Bind` *before* connecting to the database.

---

### Using third-party security mechanisms

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

Applies to

SYC Sybase Adaptive Server Enterprise

Syntax

**Sec\_Channel\_Bind** = *value*

Parameter	Description
<i>value</i>	<p>Specifies whether your connection's security mechanism performs channel binding. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do <i>not</i> perform channel binding. You can also specify 'No' or 'False' to set this value.</li> <li>• <b>1</b> Perform channel binding. Both CT-Lib and the server provide a channel identifier to the connection's security mechanism. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

Default value

Sec\_Channel\_Bind = 0

Usage

*Not supported with CyberSafe Kerberos* Sec\_Channel\_Bind is *not supported* if your security mechanism is CyberSafe Kerberos.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use Sec\_Channel\_Bind or any other parameter supporting Open Client, you must meet certain requirements for using security services in your PowerBuilder application. For details, see “Requirements for using Open Client security services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for Sec\_Channel\_Bind sets the corresponding Sybase CT-Lib connection property named CS\_SEC\_CHANBIND.

Examples

To specify that your connection's security mechanism performs channel binding:

- **Database profile** Select the Enable Channel Binding check box on the Security tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Sec_Channel_Bind=1"
```

See also

Release  
 Sec\_Cred\_Timeout  
 Sec\_Delegation  
 Sec\_Keytab\_File  
 Sec\_Mechanism  
 Sec\_Mutual\_Auth  
 Sec\_Network\_Auth  
 Sec\_Server\_Principal  
 Sec\_Sess\_Timeout

## Sec\_Confidential

**Description** When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, Sec\_Confidential is one of several parameters that support per-packet security for network-based security services. (For other per-packet security parameters, see the See Also section.)

Sec\_Confidential controls whether transmitted data is encrypted. When Sec\_Confidential is set to 1, all requests sent to the server and all results returned by the server are encrypted.

When Sec\_Confidential is set to 0 (the default), transmitted data is not encrypted.

You must specify a value for Sec\_Confidential *before* connecting to the database in PowerBuilder.

---

### Using third-party security mechanisms

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

**Applies to** SYC Sybase Adaptive Server Enterprise

**Syntax** **Sec\_Confidential** = *value*

Parameter	Description
<i>value</i>	Specifies whether transmitted data is encrypted. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do <i>not</i> encrypt transmitted data. You can also specify 'No' or 'False' to set this value.</li> <li>• <b>1</b> Encrypt transmitted data. Requests sent to the server and results returned by the server are encrypted. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

**Default value** Sec\_Confidential = 0

**Usage** *When to use* Encryption can protect your data if you are sending it over a public network to a nonsecure server. In a networked environment, you might want to set Sec\_Confidential to 1 to ensure that all requests sent to the server and all results returned by the server are encrypted.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use Sec\_Confidential or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see “Requirements for using Open Client security services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for Sec\_Confidential sets the corresponding Sybase CT-Lib connection property named CS\_SEC\_CONFIDENTIALITY.

Examples

To specify that transmitted data is encrypted:

- **Database profile** Select the Encrypt All Results check box on the Security tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Sec_Confidential=1"
```

See also

Release  
Sec\_Data\_Integrity  
Sec\_Data\_Origin  
Sec\_Replay\_Detection  
Sec\_Seq\_Detection

## Sec\_Cred\_Timeout

Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, Sec\_Cred\_Timeout is one of several parameters that support login authentication for network-based security services. (For other login authentication parameters, see the See Also section.)

Some security mechanisms allow applications to set credential timeout values for connections that use network-based login authentication.

Sec\_Cred\_Timeout specifies the number of seconds remaining before a user’s network credentials expire and become invalid. Users obtain network credentials when they log in to the network.

By default, Sec\_Cred\_Timeout specifies that there is no credential timeout limit—the credentials do not expire.

You must specify a value for Sec\_Cred\_Timeout *before* connecting to the database in PowerBuilder.



**Using third-party security mechanisms**

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

Applies to SYC Sybase Adaptive Server Enterprise

Syntax **Sec\_Cred\_Timeout** = *value*

Parameter	Description
<i>value</i>	Specifies the number of seconds remaining before a user's network credentials expire and become invalid. You can also specify 'no_limit' (the default) to specify that the credentials not expire.  A credential timeout value set by the security system's administrator supersedes any value you specify for Sec_Cred_Timeout.

Default value Sec\_Cred\_Timeout = 'no\_limit'

Usage *CyberSafe Kerberos* If your security mechanism is CyberSafe Kerberos, Sec\_Cred\_Timeout cannot override the installation default value set for credential timeout.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use Sec\_Cred\_Timeout or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see "Requirements for using Open Client security services" in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for Sec\_Cred\_Timeout sets the corresponding Sybase CT-Lib connection property named CS\_SEC\_CREDCRETIMEOUT.

Examples To specify 120 seconds (2 minutes) remaining before a user's network credentials expire:

- **Database profile** Type 120 in the Credential Timeout box on the Security tab in the Database Profile Setup dialog box.

- **Application** Type the following in code:

```
SQLCA.DBParm = "Sec_Cred_Timeout=120;Release=11"
```

See also

Release  
Sec\_Channel\_Bind  
Sec\_Delegation  
Sec\_Keytab\_File  
Sec\_Mechanism  
Sec\_Mutual\_Auth  
Sec\_Network\_Auth  
Sec\_Server\_Principal  
Sec\_Sess\_Timeout

## Sec\_Data\_Integrity

Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, `Sec_Data_Integrity` is one of several parameters that support per-packet security for network-based security services. (For other per-packet security parameters, see the See Also section.)

`Sec_Data_Integrity` controls whether your connection's security mechanism checks the integrity of data transmitted to and from the server. When `Sec_Data_Integrity` is set to 1, the security mechanism analyzes all packets to ensure that their content was not modified during transmission.

When `Sec_Data_Integrity` is set to 0 (the default), no integrity checking is performed.

You must specify a value for `Sec_Data_Integrity` *before* connecting to the database in PowerBuilder.

---

### Using third-party security mechanisms

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

Applies to

SYC Sybase Adaptive Server Enterprise

## Syntax

**Sec\_Data\_Integrity** = *value*

Parameter	Description
<i>value</i>	<p>Specifies whether your connection's security mechanism performs integrity checking on data transmitted to and from the server. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do <i>not</i> check data integrity. You can also specify 'No' or 'False' to set this value.</li> <li>• <b>1</b> Check data integrity by analyzing all packets to ensure that their content was not modified during transmission. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

## Default value

Sec\_Data\_Integrity = 0

## Usage

*When to use* Your connection's security mechanism can check data integrity only when your connection is also using network-based login authentication. For information, see your Sybase Open Client/Server documentation.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use Sec\_Data\_Integrity or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see "Requirements for using Open Client security services" in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for Sec\_Data\_Integrity sets the corresponding Sybase CT-Lib connection property named CS\_SEC\_INTEGRITY.

## Examples

To specify that your connection's security mechanism checks data integrity:

- **Database profile** Select the Ensure Data Integrity check box on the Security tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Sec_Data_Integrity=1;Release=11"
```

## See also

Release  
 Sec\_Confidential  
 Sec\_Data\_Origin  
 Sec\_Replay\_Detection  
 Sec\_Seq\_Detection

## Sec\_Data\_Origin

**Description**

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, Sec\_Data\_Origin is one of several parameters that support per-packet security for network-based security services. (For other per-packet security parameters, see the See Also section.)

Sec\_Data\_Origin controls whether your connection's security mechanism performs data origin stamping. When Sec\_Data\_Origin is set to 1, the security mechanism attaches a digital signature to each packet that verifies the packet's origin and contents.

When Sec\_Data\_Origin is set to 0 (the default), no data origin stamping is performed.

You must specify a value for Sec\_Data\_Origin *before* connecting to the database in PowerBuilder.

---

**Using third-party security mechanisms**

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

**Applies to**

SYC Sybase Adaptive Server Enterprise

**Syntax**

**Sec\_Data\_Origin = value**

Parameter	Description
value	<p>Specifies whether your connection's security mechanism performs data origin stamping. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do <i>not</i> perform data origin stamping. You can also specify 'No' or 'False' to set this value.</li> <li>• <b>1</b> Perform data origin stamping by attaching a digital signature to each packet that verifies the packet's origin and contents. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

**Default value**

Sec\_Data\_Origin = 0

**Usage**

*Not supported with CyberSafe Kerberos* Sec\_Data\_Origin is *not supported* if your security mechanism is CyberSafe Kerberos.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use `Sec_Data_Origin` or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see “Requirements for using Open Client security services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for `Sec_Data_Origin` sets the corresponding Sybase CT-Lib connection property named `CS_SEC_DATAORIGIN`.

#### Examples

To specify that your connection's security mechanism performs data origin stamping:

- **Database profile** Select the Verify Packet Origin check box on the Security tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Sec_Data_Origin=1;Release=11"
```

#### See also

Release  
 Sec\_Confidential  
 Sec\_Data\_Integrity  
 Sec\_Replay\_Detection  
 Sec\_Seq\_Detection

## Sec\_Delegation

#### Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, `Sec_Delegation` is one of several parameters that support login authentication for network-based security services. (For other login authentication parameters, see the See Also section.)

For applications that are using network-based login authentication to connect to a Sybase Open Server gateway, `Sec_Delegation` controls whether the gateway server is allowed to connect to a remote SQL Server using delegated credentials. When `Sec_Delegation` is set to 1, the gateway can connect to a remote server using the client's delegated credentials. The remote server must also be using network-based authentication and an identical security mechanism.

When `Sec_Delegation` is set to 0 (the default), the gateway server cannot connect to a remote server using delegated credentials.

You must specify a value for `Sec_Delegation` *before* connecting to the database in PowerBuilder.

**Using third-party security mechanisms**

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

Applies to

SYC Sybase Adaptive Server Enterprise

Syntax

**Sec\_Delegation** = *value*

Parameter	Description
<i>value</i>	<p>Specifies whether the Sybase Open Server gateway is allowed to connect to a remote SQL Server using the client's delegated credentials. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Prohibit the gateway from connecting to a remote server using delegated credentials. You can also specify 'No' or 'False' to set this value.</li> <li>• <b>1</b> Allow the gateway to connect to a remote server using delegated credentials. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

Default value

Sec\_Delegation = 0

Usage

*Not supported with CyberSafe Kerberos* Sec\_Delegation is *not supported* if your security mechanism is CyberSafe Kerberos.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use Sec\_Delegation or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see "Requirements for using Open Client security services" in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for Sec\_Delegation sets the corresponding Sybase CT-Lib connection property named CS\_SEC\_DELEGATION.

Examples

To allow the Open Server gateway to connect to a remote server using delegated credentials:

- **Database profile** Select the Use Delegated Credentials check box on the Security tab in the Database Profile Setup dialog box.

- **Application** Type the following in code:

```
SQLCA.DBParm = "Sec_Delegation=1;Release=11"
```

See also

Release  
 Sec\_Channel\_Bind  
 Sec\_Cred\_Timeout  
 Sec\_Keytab\_File  
 Sec\_Mechanism  
 Sec\_Mutual\_Auth  
 Sec\_Network\_Auth  
 Sec\_Server\_Principal  
 Sec\_Sess\_Timeout

## Sec\_Keytab\_File

Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, `Sec_Keytab_File` is one of several parameters that support login authentication for network-based security services. (For other login authentication parameters, see the See Also section.)

`Sec_Keytab_File` applies only to connections using Distributed Computing Environment (DCE) Kerberos as their security mechanism and requesting network-based login authentication. For those connections, `Sec_Keytab_File` specifies the name of the keytab file containing the security key for the DCE user.

You *must* set `Sec_Keytab_File` if the login ID specified in the database profile or `Application` is *different* from the user name of the DCE user currently running the application.

You must specify a value for `Sec_Keytab_File` *before* connecting to the database in PowerBuilder.

---

### Using third-party security mechanisms

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

Applies to

SYC Sybase Adaptive Server Enterprise

Syntax **Sec\_Keytab\_File = 'keytab\_filename'**

Parameter	Description
<i>keytab_filename</i>	The name of the keytab file containing the security key for the DCE user

Default value None

PowerBuilder does not set Sec\_Keytab\_File or the corresponding Sybase Open Client Client-Library (CT-Lib) connection parameter CS\_SEC\_KEYTAB if you do not specify a value.

Usage *Supported only with Distributed Computing Environment* Only Distributed Computing Environment (DCE) security servers and clients support the use of keytab files. Therefore, Sec\_Keytab\_File is supported only when your security mechanism is DCE Kerberos.

*When to use* If you want your application to be able to connect to a server with a different user name (login ID) than the DCE user currently running the application, set Sec\_Keytab\_File to specify the name of the keytab file containing the security key for the appropriate user. For details, see “Requirements for using Open Client security services” in *Connecting to Your Database*.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use Sec\_Keytab\_File or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see “Requirements for using Open Client security services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for Sec\_Keytab\_File sets the corresponding Sybase CT-Lib connection property named CS\_SEC\_KEYTAB.

Examples To specify C:\DCE\_KEY as the name of the DCE keytab file:

- **Database profile** Type the following in the Keytab File box on the Security tab in the Database Profile Setup dialog box:

C:\DCE\_KEY



- **Application** Type the following in code:

```
SQLCA.DBParm =
"Sec_Keytab_File='C:\DCE_KEY';Release=11"
```

See also

Release  
 Sec\_Channel\_Bind  
 Sec\_Cred\_Timeout  
 Sec\_Delegation  
 Sec\_Mechanism  
 Sec\_Mutual\_Auth  
 Sec\_Network\_Auth  
 Sec\_Server\_Principal  
 Sec\_Sess\_Timeout

## Sec\_Mechanism

Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, `Sec_Mechanism` is one of several parameters that support login authentication for network-based security services. (For other login authentication parameters, see the See Also section.)

When you use Open Client security services, you must specify the name of the security mechanism you want to use in the Open Client/Open Server Configuration utility so that the required drivers can be loaded. The default security mechanism is the one currently specified as active in the Configuration utility.

`Sec_Mechanism` lets you specify a security mechanism name listed in the Open Client/Open Server Configuration utility *other than* the default (active) mechanism.

You must specify a value for `Sec_Mechanism` *before* connecting to the database in PowerBuilder.

---

### Using third-party security mechanisms

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

Applies to

SYC Sybase Adaptive Server Enterprise

Syntax

**Sec\_Mechanism** = '*mechanism\_name*'

Parameter	Description
<i>mechanism_name</i>	<p>The security mechanism name you want to use to establish a connection.</p> <p>The security mechanism name is case sensitive. You must specify it <i>exactly as it appears</i> in the Open Client/Open Server Configuration utility.</p>

Default value

The default value for Sec\_Mechanism is the security mechanism name currently specified as active in the Open Client/Open Server Configuration utility. If there is no security mechanism specified, no security service is used to establish the connection.

Usage

*When to use* Set Sec\_Mechanism to use a security mechanism specified in the Open Client/Open Server Configuration utility *other than* the default (active) security mechanism. For instructions on using the Open Client/Open Server Configuration utility, see your Sybase Open Client/Server configuration guide.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use Sec\_Mechanism or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see “Requirements for using Open Client security services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for Sec\_Mechanism sets the corresponding Sybase CT-Lib connection property named CS\_SEC\_MECHANISM.

Examples

To specify KERBEROS as your security mechanism name:

- **Database profile** Type the following in the Security Mechanism box on the Security tab in the Database Profile Setup dialog box:

```
KERBEROS
```

- **Application** Type the following in code:

```
SQLCA.DBParm =  
"Sec_Mechanism='KERBEROS';Release=11"
```

See also           Release  
                  Sec\_Channel\_Bind  
                  Sec\_Cred\_Timeout  
                  Sec\_Delegation  
                  Sec\_Keytab\_File  
                  Sec\_Mutual\_Auth  
                  Sec\_Network\_Auth  
                  Sec\_Server\_Principal  
                  Sec\_Sess\_Timeout

## Sec\_Mutual\_Auth

**Description**           When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, Sec\_Mutual\_Auth is one of several parameters that support login authentication for network-based security services. (For other login authentication parameters, see the See Also section.)

Sec\_Mutual\_Auth controls whether your connection's security mechanism performs mutual authentication. When Sec\_Mutual\_Auth is set to 1, the server must prove its identity to the client before connecting by sending a credential token containing the server's principal name and proof that this name is authentic.

When Sec\_Mutual\_Auth is set to 0 (the default), no mutual authentication is performed.

You must specify a value for Sec\_Mutual\_Auth *before* connecting to the database in PowerBuilder.

---

### Using third-party security mechanisms

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

**Applies to**           SYC Sybase Adaptive Server Enterprise

**Syntax**               **Sec\_Mutual\_Auth = value**

Parameter	Description
<i>value</i>	<p>Specifies whether your connection's security mechanism performs mutual authentication. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Does <i>not</i> perform mutual authentication. You can also specify 'No' or 'False' to set this value.</li> <li>• <b>1</b> Performs mutual authentication. The server must prove its identity to the client before connecting by sending a credential token containing the server's principal name and proof that this name is authentic. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

Default value

Sec\_Mutual\_Auth = 0

Usage

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use Sec\_Mutual\_Auth or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see "Requirements for using Open Client security services" in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for Sec\_Mutual\_Auth sets the corresponding Sybase CT-Lib connection property named CS\_SEC\_MUTUALAUTH.

Examples

To specify that your connection's security mechanism performs mutual authentication:

- **Database profile** Select the Mutual Authentication check box on the Security tab in the Database Profile dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Sec_Mutual_Auth=1;Release=11"
```

See also

Release  
 Sec\_Channel\_Bind  
 Sec\_Cred\_Timeout  
 Sec\_Delegation  
 Sec\_Keytab\_File  
 Sec\_Mechanism  
 Sec\_Network\_Auth  
 Sec\_Server\_Principal  
 Sec\_Sess\_Timeout

## Sec\_Network\_Auth

**Description** When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, `Sec_Network_Auth` is one of several parameters that support login authentication for network-based security services. (For other login authentication parameters, see the See Also section.)

`Sec_Network_Auth` controls whether your connection uses network-based login authentication. When `Sec_Network_Auth` is set to 1, your connection uses network-based authentication when connecting to a secure SQL Server. **Network-based authentication** means that the security mechanism—not the application—confirms that the specified user name represents the authenticated user running the application.

Since the security mechanism rather than the application authenticates your user name (login ID), you need *not* supply a login password for authentication purposes in the database profile or Application if `Sec_Network_Auth` is set to 1.

When `Sec_Network_Auth` is set to 0 (the default), your connection does not use network-based login authentication to connect to the server. You must specify a value for `Sec_Network_Auth` *before* connecting to the database in PowerBuilder.

---

### Using third-party security mechanisms

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

**Applies to** SYC Sybase Adaptive Server Enterprise

**Syntax** `Sec_Network_Auth = value`

Parameter	Description
<i>value</i>	<p>Specifies whether your connection uses network-based login authentication when connecting to a secure SQL Server. Values are:</p> <ul style="list-style-type: none"> <li><b>0</b> (Default) Does <i>not</i> use network-based login authentication when connecting to the server. You can also specify 'No' or 'False' to set this value.</li> <li><b>1</b> Uses network-based login authentication when connecting to the server. Since the security mechanism rather than the application authenticates your user name (login ID), you need <i>not</i> supply a login password for authentication purposes in the database profile or Application. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

Default value	Sec_Network_Auth = 0
Usage	<p><i>When to use</i> Setting Sec_Network_Auth to 1 to enable network-based login authentication provides three important benefits for PowerBuilder users, because you do not have to specify a login password in the database profile or Application to authenticate the login ID when Sec_Network_Auth is set to 1:</p> <ul style="list-style-type: none"><li>• <b>Password not stored in registry file</b> Since you do not specify a login password, no login password is stored in the Windows registry.</li><li>• <b>Password not transmitted across network</b> Since you do not specify a login password, no login password is transmitted across the network to Adaptive Server.</li><li>• <b>Same user ID and password for different servers</b> You can use the same network user ID and password to connect to many different Adaptive Server database servers. You can change your password for the network security mechanism and have this change apply on all servers to which your application connects.</li></ul> <p><i>Set Release parameter</i> For this parameter to take effect, you <i>must</i> also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.</p> <p><i>Requirements for use</i> To use Sec_Network_Auth or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see “Requirements for using Open Client security services” in <i>Connecting to Your Database</i>.</p> <p><i>Corresponding CT-Lib connection property</i> Specifying a value for Sec_Network_Auth sets the corresponding Sybase CT-Lib connection property named CS_SEC_NETWORKAUTH.</p>
Examples	<p>To specify that your connection uses network-based login authentication when connecting to the server:</p> <ul style="list-style-type: none"><li>• <b>Database profile</b> Select the Network Based Authentication check box on the Security tab in the Database Profile Setup dialog box.</li><li>• <b>Application</b> Type the following in code: <pre>SQLCA.DBParm = "Sec_Network_Auth=1;Release=11"</pre></li></ul>
See also	Release Sec_Channel_Bind Sec_Cred_Timeout Sec_Delegation Sec_Keytab_File Sec_Mechanism

Sec\_Mutual\_Auth  
 Sec\_Server\_Principal  
 Sec\_Sess\_Timeout

## Sec\_Replay\_Detection

### Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, `Sec_Replay_Detection` is one of several parameters that support per-packet security for network-based security services. (For other per-packet security parameters, see the See Also section.)

`Sec_Replay_Detection` controls whether your connection's security mechanism can detect and reject unauthorized attempts to capture and replay transmitted data. When `Sec_Replay_Detection` is set to 1, the security mechanism detects and subsequently rejects any unauthorized attempts by third parties to capture packets sent to the server and repeat (replay) the commands in the packets at a later time.

When `Sec_Replay_Detection` is set to 0 (the default), the security mechanism cannot detect unauthorized attempts to capture and replay data.

You must specify a value for `Sec_Replay_Detection` *before* connecting to the database in PowerBuilder.

---

### Using third-party security mechanisms

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

### Applies to

SYC Sybase Adaptive Server Enterprise

### Syntax

**Sec\_Replay\_Detection** = *value*

Parameter	Description
<i>value</i>	<p>Specifies whether your connection's security mechanism can detect and reject unauthorized attempts to capture and replay transmitted data. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Prohibits your security mechanism from detecting unauthorized attempts to capture and replay transmitted data. You can also specify 'No' or 'False' to set this value.</li> <li>• <b>1</b> Allows your security mechanism to detect and reject unauthorized attempts to capture and replay transmitted data. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

Default value	Sec_Replay_Detection = 0
Usage	<p><i>When to use</i> In a nonsecure network, unauthorized third parties might capture the commands sent to a server in order to repeat (replay) these commands at a later date. For example, if packets are sent from the client to the server in the order P1, P2, P3 and the server receives the packets in the order P1, P3, P2, this is considered an attempt to replay the data. Setting Sec_Replay_Detection to 1 ensures that your security mechanism can detect and subsequently reject all such unauthorized attempts to capture and replay data transmitted over the network.</p> <p><i>Set Release parameter</i> For this parameter to take effect, you <i>must</i> also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.</p> <p><i>Requirements for use</i> To use Sec_Replay_Detection or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see “Requirements for using Open Client security services” in <i>Connecting to Your Database</i>.</p> <p><i>Corresponding CT-Lib connection property</i> Specifying a value for Sec_Replay_Detection sets the corresponding Sybase CT-Lib connection property named CS_SEC_DETECTREPLAY.</p>
Examples	<p>To allow your security mechanism to detect and reject unauthorized attempts to capture and replay transmitted data:</p> <ul style="list-style-type: none"><li>• <b>Database profile</b> Select the Detect Replayed Commands check box on the Security tab in the Database Profile Setup dialog box.</li><li>• <b>Application</b> Type the following in code:<pre>SQLCA.DBParm = "Sec_Replay_Detection=1;Release=12.5"</pre></li></ul>
See also	Release Sec_Confidential Sec_Data_Integrity Sec_Data_Origin Sec_Seq_Detection



## Sec\_Seq\_Detection

**Description** When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, `Sec_Seq_Detection` is one of several parameters that support per-packet security for network-based security services. (For other per-packet security parameters, see the See Also section.)

`Sec_Seq_Detection` controls whether your connection's security mechanism can detect and reject transmitted packets that arrive at the server in a different order than was originally sent from the client. When `Sec_Seq_Detection` is set to 1, the security mechanism detects and rejects packets that arrive at the server out of sequence.

When `Sec_Seq_Detection` is set to 0 (the default), the security mechanism cannot detect packets that arrive at the server out of sequence.

You must specify a value for `Sec_Seq_Detection` *before* connecting to the database in PowerBuilder.

---

### Using third-party security mechanisms

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

**Applies to** SYC Sybase Adaptive Server Enterprise

**Syntax** `Sec_Seq_Detection = value`

Parameter	Description
<i>value</i>	Specifies whether your connection's security mechanism can detect and reject packets that arrive at the server in a different order than the one in which they were sent from the client. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Prohibit your security mechanism from detecting packets that arrive at the server out of sequence. You can also specify 'No' or 'False' to set this value.</li> <li>• <b>1</b> Allow your security mechanism to detect and reject packets that arrive at the server out of sequence. You can also specify 'Yes' or 'True' to set this value.</li> </ul>

**Default value** `Sec_Seq_Detection = 0`

**Usage** *When to use* When transmitting data over a network, commands sent to a server might arrive out of sequence. For example, if packets are sent from the client to the server in the order P1, P2, P3 and the server receives the packets in the order P1, P3, P2, this is considered an out-of-sequence error.

Setting `Sec_Seq_Detection` to 1 ensures that your security mechanism can detect and subsequently reject packets that arrive at the server out of sequence.

*Set Release parameter* For this parameter to take effect, you *must* also set the `Release` parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the `Release` parameter for more information.

*Requirements for use* To use `Sec_Seq_Detection` or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see “Requirements for using Open Client security services” in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for `Sec_Seq_Detection` sets the corresponding Sybase CT-Lib connection property named `CS_SEC_DETECTSEQ`.

Examples

To allow your security mechanism to detect and reject packets that arrive at the server out of sequence:

- **Database profile** Select the Detect Sequence Errors check box on the Security tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Sec_Seq_Detection=1;Release=12.5"
```

See also

`Release`  
`Sec_Confidential`  
`Sec_Data_Integrity`  
`Sec_Data_Origin`  
`Sec_Replay_Detection`

## Sec\_Server\_Principal

Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, `Sec_Server_Principal` is one of several parameters that support login authentication for network-based security services. (For other login authentication parameters, see the See Also section.)

`Sec_Server_Principal` specifies the principal name of the server that you want to access. The **server principal name** is the name by which your security mechanism identifies each server.

If the server name (specified in the database profile or Application) is *different* from the server principal name for the server you want to access, you *must* set `Sec_Server_Principal` to the correct server principal name in order to connect.

You must specify a value for `Sec_Server_Principal` *before* connecting to the database in PowerBuilder.

---

### Using third-party security mechanisms

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

Applies to

SYC Sybase Adaptive Server Enterprise

Syntax

**Sec\_Server\_Principal** = 'server\_principal\_name'

Parameter	Description
<i>server_principal_name</i>	Specifies the principal name of the server you want to access

Default value

None

If you do not specify a value, the security mechanism uses the server's directory entry name, which is the same as the server name specified in the database profile or Application.

Usage

*When to use* When you use Open Client security services with PowerBuilder, the server's directory entry name (which you specify as the server name in the database profile or Application) might differ from the server principal name. In this case, you *must* set `Sec_Server_Principal` to the correct server principal name so that the security mechanism can identify the server you want to access.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use `Sec_Server_Principal` or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see "Requirements for using Open Client security services" in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for Sec\_Server\_Principal sets the corresponding Sybase CT-Lib connection property named CS\_SEC\_SERVERPRINCIPAL.

Examples

To specify SYS12NT as the principal name of the server you want to access:

- **Database profile** Type SYS12NT in the Server Principal Name box on the Security tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm =  
"Sec_Server_Principal='SYS12NT';Release=12"
```

See also

Release  
Sec\_Channel\_Bind  
Sec\_Cred\_Timeout  
Sec\_Delegation  
Sec\_Keytab\_File  
Sec\_Mechanism  
Sec\_Mutual\_Auth  
Sec\_Network\_Auth  
Sec\_Sess\_Timeout

## Sec\_Sess\_Timeout

Description

When you access a Sybase Adaptive Server Enterprise database in PowerBuilder through Open Client, Sec\_Sess\_Timeout is one of several parameters that support login authentication for network-based security services. (For other login authentication parameters, see the See Also section.)

Some security mechanisms allow applications to set session timeout values for connections using network-based login authentication. For these connections, Sec\_Sess\_Timeout specifies the number of seconds remaining before a session expires. The session timeout period begins when the connection is opened.

By default, Sec\_Sess\_Timeout specifies that there is no session timeout limit; the session does not expire. You must specify a value for Sec\_Sess\_Timeout *before* connecting to the database in PowerBuilder.

---

### Using third-party security mechanisms

For information about the third-party security mechanisms and operating system platforms that Sybase has tested with Open Client security services, see the Open Client documentation.

---

Applies to

SYC Sybase Adaptive Server Enterprise

## Syntax

**Sec\_Sess\_Timeout** = *value*

Parameter	Description
<i>value</i>	Specifies the number of seconds remaining before a session expires. You can also specify 'no_limit' (the default) to indicate that the session does not expire.  A session timeout value set by the security system's administrator supersedes any value you specify for Sec_Sess_Timeout.

## Default value

Sec\_Sess\_Timeout = 'no\_limit'

## Usage

*CyberSafe Kerberos* If your security mechanism is CyberSafe Kerberos, Sec\_Sess\_Timeout cannot override the installation default value set for session timeout.

*Set Release parameter* For this parameter to take effect, you *must* also set the Release parameter to 11 or higher to specify that your application should use the appropriate version of Sybase Open Client Client-Library (CT-Lib) behavior. See the description of the Release parameter for more information.

*Requirements for use* To use Sec\_Sess\_Timeout or any other parameter supporting Open Client security services, you must meet certain requirements for using security services in your PowerBuilder application. For details, see "Requirements for using Open Client security services" in *Connecting to Your Database*.

*Corresponding CT-Lib connection property* Specifying a value for Sec\_Sess\_Timeout sets the corresponding Sybase CT-Lib connection property named CS\_SEC\_SESSTIMEOUT.

## Examples

To specify 14,400 seconds (4 hours) remaining before a session expires:

- **Database profile** Type 14400 in the Session Timeout box on the Security tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Sec_Sess_Timeout=14400"
```

## See also

Release  
 Sec\_Channel\_Bind  
 Sec\_Cred\_Timeout  
 Sec\_Delegation  
 Sec\_Keytab\_File  
 Sec\_Mechanism  
 Sec\_Mutual\_Auth  
 Sec\_Network\_Auth  
 Sec\_Server\_Principal

## ServiceComponents

Description Specifies the global services the OLE DB interface can use.

---

### When to specify ServiceComponents

You must specify the ServiceComponents parameter *before* connecting to the database.

---

Applies to OLE DB

Syntax **ServiceComponents** = 'servicecomponent\_name'

Default value None

Examples To enable the resource pooling service component:

- **Database profile** Select Resource Pooling from the Service Component Support box on the System tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm =  
"ServiceComponents='DBPROPVAL_OS_RESOURCEPOOLING' "
```

## ShowWarnings

Description Specifies whether warning message text can be concatenated to existing error messages.

Applies to DIR Sybase DirectConnect

Syntax **ShowWarnings** = *value*

Parameter	Description
<i>value</i>	Specifies whether warning message text can be concatenated to existing error messages. Values are: <ul style="list-style-type: none"><li>• <b>0</b> (Default) Does not allow the concatenation of warning message text to existing error messages.</li><li>• <b>1</b> Allows the concatenation of warning message text to existing error messages.</li></ul>

Default value ShowWarnings = 0

**Usage** The ShowWarnings parameter allows the DirectConnect interface to use warning and error processing similar to that formerly available in the InformationConnect DB2 Gateway (MDI) interface. For example, if a single warning message appears on the DIR error queue, the default behavior is to discard warnings. If ShowMessages is set, `sqlca.sqlcode = -1` and `sqlca.sqlerrtext = "text_of_warning_message"` are returned to the application.

`sqlca.sqlerrtext` cannot exceed 254 characters. Consequently, if multiple warning messages are returned together, message text might be truncated.

For Access Service connections, must be issued before connecting to ensure its correct operation.

**Examples** To specify that you want to show warning messages as errors:

- **Database profile** Select the Show Warning Messages as Errors check box on the Syntax tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "ShowWarnings=1"
```

## SPCache

**Description** Specifies the number of stored procedures for which the ADO.NET driver caches information.

---

### When to specify SPCache

If you want to change the default value for SPCache, you must specify a new value *before* connecting to the database. The value cannot be changed at runtime.

---

**Applies to** ADO.NET

**Syntax** `SPCache = value`

Parameter	Description
<i>value</i>	A number that specifies how many stored procedures are added to a cache that contains information about each stored procedure's parameters. To turn off caching, specify 0.

**Default value** SPCache=50

**Usage** By default, the ADO.NET driver retrieves information from the server about a stored procedure's parameters the first time the stored procedure is called and caches that information. The next time the procedure is called, the driver retrieves the information from the cache to improve performance. The information is retrieved based on the stored procedure's name. The name is case sensitive.

If you call two different stored procedures with the same name, you can turn off caching by setting the value of SPCache to 0.

**Examples**

To turn off caching of stored procedure parameter information:

- **Database profile** Specify 0 in the Maximum Procedures to Cache box on the System tab page in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm= "SPCache=0"
```

## SQLCache

**Description**

Specifies the number of SQL statements that PowerBuilder should cache. The default is 0, specifying an empty SQL cache.

PowerBuilder caches:

- SQL statements generated by a DataWindow object or report
- Embedded SQL statements

**Applies to**

ODBC

**Syntax**

**SQLCache** = *value*

Parameter	Description
<i>value</i>	The number of cursors you want to open in a script, plus the number of DataWindow-generated SELECT statements with retrieval arguments (default = 0).

**Default value**

SQLCache = 0

**Usage**

**Note** The SQLCache parameter is present in the Database Profile Setup dialog box for Oracle connections. However, for Oracle 8.x and later, Oracle OCI handles caching and setting SQLCache is not recommended.

---



*Maintaining statements in the cache* Statements in the SQL cache are maintained on a least-recently-used (**LRU**) basis. In other words, if a statement must be removed from the cache to make room for another statement, PowerBuilder removes the statement that was least recently executed.

*SQLCache and bind variables* Caching SQL statements that you execute frequently improves their performance. Statements with bind variables are often the most frequently used. In fact, if your DBMS does not support bind variables, caching statements is of limited value.

*Setting DisableBind to use cached statements* In order to use cached statements, make sure the `DisableBind` parameter is set to 0 (the default). This enables the binding of input variables to SQL statements.

For more about using bind variables, see `DisableBind`.

*What happens* The first time you execute a SQL statement containing bind variables, PowerBuilder does the following in this sequence:

- 1 Parses the statement.
- 2 For SQL `SELECT` statements, calls the appropriate database function to get a description of the result set.
- 3 Allocates memory buffers for the bind variables.
- 4 Binds the allocated memory buffers to the parsed statement.

When you cache this SQL statement, PowerBuilder stores the parsed statement, result set description, and memory buffer allocation and binding in the SQL cache. The next time you execute this statement, PowerBuilder finds it in the cache and avoids the overhead of repeating these steps.

If PowerBuilder finds an exact match for this statement in the SQL cache, it simply copies the new values supplied for the bind variables to the preallocated memory buffers and executes the statement. This is much faster than having to process the statement from scratch.

*Determining the size of your SQL cache* To determine an appropriate size for your SQL cache, you can check the value of the `SqlReturnData` property of the `Transaction` object.

When you disconnect from the database, the number of hits, misses, and entries in the SQL cache is stored in `SqlReturnData` as follows:

- **Hits** The number of times PowerBuilder found a matching statement in the SQL cache

- **Misses** The number of times PowerBuilder did not find a matching statement in the cache
- **Entries** The total number of statements in the SQL cache, which is determined by your SQLCache setting

Examples

To set the SQL cache size to 25 statements:

- **Database profile** Type 25 in the Number Of SQL Statements Cached box on the Transaction tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "SQLCache=25"
```

See also

DisableBind

## SQLQualifiers

Description

Sets the level of qualification for identifiers (table and column names) in SQL statements when you connect to a database. This affects behavior in DataWindow objects.

When PowerBuilder **qualifies** a table or column name, it prefixes it with the name of the owner. For example, if a user named Fran owns a table named Sales, the qualified table name is Fran.Sales.

Applies to

DIR Sybase DirectConnect

Syntax

**SQLQualifiers** = *value*

Parameter	Description
<i>value</i>	<p>Sets the level of qualification for identifiers in SQL statements when you connect to a database. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not qualify identifiers with owner names in SQL statements.</li> <li>• <b>1</b> Qualify identifiers with owner names in SQL statements.</li> </ul>

Default value

SQLQualifiers = 0

Usage

*When PowerBuilder qualifies identifiers* If the name of the table owner is the same as the name of the user logged in to the database, PowerBuilder does not qualify identifiers with owner names in the SQL statements it generates. If you set the SQLQualifiers parameter to 1, PowerBuilder qualifies identifiers with an owner name in SQL statements.

Examples To specify that you want PowerBuilder to qualify identifiers with owner names in SQL statements:

- **Database profile** Select the Qualify Identifiers With Owner Names check box on the Syntax tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "SQLQualifiers=1"
```

## StaticBind

Description When you retrieve data from a database into a DataWindow object or report, PowerBuilder does not get a result set description to validate the SELECT statement against the database server before retrieving the data. This means the retrieval should be faster, especially when you are accessing the database over a network. (This feature is called **describeless retrieval**.)

If you want to override the default behavior and have PowerBuilder get a description of the result set before retrieving data, set the StaticBind parameter to 0 or No.

Applies to ADO.NET  
DIR Sybase DirectConnect  
JDB JDBC  
ODBC  
OLE DB  
O84 Oracle 8.x and Oracle8i  
O90 Oracle9i  
O10 Oracle 10g  
SYC and SYJ Sybase Adaptive Server Enterprise

Syntax **StaticBind** = *value*

Parameter	Description
<i>value</i>	Specifies whether you want PowerBuilder to get a result set description before retrieving data from a database into a DataWindow object or report. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> Get a result set description before retrieving data. You can also specify 'No' to set this value.</li> <li>• <b>1</b> (Default) Skip getting a result set description before retrieving data. You can also specify 'Yes' to set this value.</li> </ul>

Default value StaticBind = 1

Usage

*Validation* When StaticBind is set to 1 (the default), PowerBuilder does not validate the SELECT statement against the database server before retrieving data. It assumes that the result set matches the column format of the DataWindow object or report into which it is being retrieved. If a mismatch occurs, PowerBuilder displays an error.

*Troubleshooting tips* Problems can occur in your application if the result set description obtained by the DataWindow object or report is different from the current database description of the result set. This can occur for the following reasons:

- The database definition changes after you build the DataWindow object or report.
- You build the DataWindow object or report while connected to one DBMS and then run it against a different DBMS.

To fix problems caused by conflicting result set descriptions, you can correct your DataWindow object or report definition by doing either of the following:

- Export and edit your column definitions
- Force a recompile of the SQL statement in the Database painter's Interactive SQL (ISQL) view (see the *User's Guide* for instructions)

If your DataWindow object or report and DBMS result set descriptions do not match and you want to avoid errors, set StaticBind to 0 or No to specify that PowerBuilder should *always* get a result set description before retrieving data into a DataWindow object or report.

Examples

To specify that you want PowerBuilder to get a result set description before retrieving data into a DataWindow object or report:

- **Database profile** Clear the Static Bind check box on the Transaction tab (or System tab in the case of the OLE DB interface) in the Database Profile Setup dialog box.
- **Application** To specify this statement in code, type the following:

```
SQLCA.DBParm = "StaticBind=0"
```

## StripParmNames

**Description** Specifies that explicitly named parameters should not be passed to the ODBC driver.

**Applies to** ODBC

**Syntax** `StripParmNames='value'`

Parameter	Description
<i>value</i>	<p>Specifies that explicitly named parameters should not be passed to the ODBC driver. Values are:</p> <ul style="list-style-type: none"> <li>• <b>Yes</b> Remove all parameter names from the generated call escape syntax.</li> <li>• <b>No</b> (Default) Keep parameter names that are explicitly specified and include them in the generated call escape syntax.</li> </ul>

**Default value** `StripParmNames='No'`

**Usage** By default, PowerBuilder retains parameter names if explicitly specified in the execution of a stored procedure. As a result, syntax such as the following might be generated and sent to the ODBC driver:

```
{call proc(a=?,b=?)}
```

Some database vendors do not allow parameter names to be specified in the generated call escape syntax. To prevent the passing of explicitly named parameters to the ODBC driver, set `StripParmNames` to `Yes`. This means that the parameters are passed in the order specified.

**Examples** To strip explicitly stated parameter names from a stored procedure:

- **Database profile** Select the Strip Parameter Names check box on the Syntax tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "StripParmNames='Yes' "
```

## SvrFailover

**Description** Specifies whether you want PowerBuilder to recognize and participate in failover to a designated backup database server if the current database server goes down.

---

### When to specify SvrFailover

You must specify the SvrFailover parameter *before* connecting to the database.

---

**Applies to** O84 Oracle 8.x and Oracle8i (8.1.5 and higher database connections only)  
O90 Oracle9i  
O10 Oracle 10g  
SYC Sybase Adaptive Server Enterprise (12.0 and higher database connections only)  
SYJ Sybase Adaptive Server Enterprise

**Syntax** **SvrFailover='value'**

Parameter	Description
<i>value</i>	Specifies whether you want PowerBuilder to recognize and participate in failover to a designated backup database server if the current database server goes down. Values are: <ul style="list-style-type: none"><li>• <b>No</b> (Default) PowerBuilder should not recognize or participate in failover.</li><li>• <b>Yes</b> PowerBuilder should recognize and participate in failover.</li></ul>

**Default value** SvrFailover = 'No'

**Usage** Both Oracle and Sybase support database server failover in Oracle Version 8.1.5 or later and Adaptive Server 12 or later. For information about how to configure failover for these database servers, see your Oracle or Adaptive Server documentation. To avoid losing your PowerBuilder database connection (as the result of a timeout) when a failover takes place, set the SvrFailover parameter so that PowerBuilder recognizes and participates in the database server failover.

Oracle also allows you some control over the failover process. Three additional parameters allow you to specify the number of times you want the database server to which you are connected to attempt a failover, how long to wait between failover attempts, and whether PowerBuilder should display a runtime dialog box indicating when a failover occurs.

This parameter cannot be set dynamically. The value set when the connection is made remains in effect until it is disconnected.

- Examples To tell PowerBuilder to recognize and participate in failover:
- **Database profile** Select the Allow Server Failover check box on the Network tab in the Database Profile Setup dialog box.
  - **Application** Type the following in code:
 

```
SQLCA.DBParm = "SvrFailover='Yes'"
```
- See also FoDelay  
FoDialog  
FoRetryCount

## SystemOwner

Description Specifies the owner of the IBM DB2 system tables that you want PowerBuilder to use. PowerBuilder accesses the DB2 system tables to get information about the tables and columns in your database.

Applies to DIR Sybase DirectConnect

Syntax **SystemOwner** = '*owner\_name*'

Parameter	Description
<i>owner_name</i>	Specifies the owner of the DB2 system tables that you want PowerBuilder to use (default = SYSIBM)

Default value SystemOwner = 'SYSIBM'

Usage When you use the SystemOwner parameter to specify a nondefault system owner, PowerBuilder uses the set of system tables belonging to this owner instead of the default system tables owned by SYSIBM.

If your site has a large DB2 system catalog, it might be useful to create local copies of the catalog tables and populate them with a subset of the information in the default system catalog. These local copies are sometimes called **shadow catalogs**.

You can then set the value of SystemOwner to the owner of the shadow catalogs. This tells PowerBuilder to access the smaller shadow catalogs instead of the larger default system tables, resulting in faster performance. However, you must make sure to keep the shadow catalogs synchronized with the default system catalog owned by SYSIBM.

For more about creating shadow catalogs, see your DB2 system administrator or check whether there is a technical document that describes how to do it. Updated information about connectivity issues is available from the Sybase Customer Service and Support Web site at <http://www.sybase.com/support>.

Examples

To specify MYAPP as the owner of the system tables that you want PowerBuilder to use:

- **Database profile** Type `MYAPP` in the CSP Catalog Qualifier box on the System tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "SystemOwner='MYAPP' "
```

## SystemProcs

Description

Specifies whether you want PowerBuilder to display both system-stored procedures and user-defined stored procedures in the connected database when you request a list of stored procedures.

By default, PowerBuilder displays both system and user-defined stored procedures in the connected database. If you set SystemProcs to 0 or No, only user-defined stored procedures are displayed.

Applies to

SYC Sybase Adaptive Server Enterprise

Syntax

**SystemProcs = value**

Parameter	Description
<i>value</i>	<p>Specifies whether you want PowerBuilder to display both system-stored procedures and user-defined stored procedures in the connected database when you request a list of stored procedures. Values are:</p> <ul style="list-style-type: none"> <li>• <b>0</b> Display only user-defined stored procedures. You can also specify 'No' to set this value.</li> <li>• <b>1</b> (Default) Display both system-stored procedures and user-defined stored procedures. You can also specify 'Yes' to set this value.</li> </ul>

Default value

SystemProcs = 1

Usage

Setting SystemProcs to 0 or No speeds response time if you want to work only with user-defined stored procedures.



Examples	<p>To specify that you want PowerBuilder to display only user-defined stored procedures in the connected database when you request a list of stored procedures:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Clear the Display System Stored Procedures check box on the System tab in the Database Profile Setup dialog box.</li> <li>• <b>Application</b> To specify this statement in code, type the following: <pre style="margin-left: 40px;">SQLCA.DBParm = "SystemProcs=0"</pre> </li> </ul>
<b>TableCriteria</b>	
Description	<p>Lets you specify search conditions to limit the list of tables and views that displays in the Installed Database Interfaces Tables list in PowerBuilder. Setting this parameter can be useful if you are working with a very large database in the PowerBuilder development environment.</p> <hr/> <p><b>When to specify TableCriteria</b> You must specify the TableCriteria parameter <i>before</i> connecting to the database.</p> <p>The TableCriteria parameter has no effect in a PowerBuilder application script.</p> <hr/>
Applies to	<p>DIR Sybase DirectConnect JDB JDBC ODBC O84 Oracle 8.x and Oracle8i O90 Oracle9i O10 Oracle 10g SYC Sybase Adaptive Server Enterprise</p>
Syntax	<p>You specify the TableCriteria search conditions on the System tab in the Database Profile Setup dialog box.</p>
Default value	<p>None. If you do not specify any values, the TableCriteria parameter is not used.</p> <p><b>Oracle</b> If you do not specify a value for TableCriteria, all Oracle tables, views, and synonyms that you have permission to access display in the Installed Database Interfaces Tables list by default.</p>

Usage

To specify the TableCriteria search conditions, enter information in the following boxes:

Field	Description
Table Name	<p>Specifies the names of tables to display in the current database. You can use wildcard characters.</p> <p><b>Default for DirectConnect interface</b> If you omit this value when connected through the DirectConnect interface, PowerBuilder displays all tables that you have permission to access in the current database, as defined in the DirectConnect server configuration file.</p> <p><b>Default for Adaptive Server Enterprise interface</b> If you omit this value when connected through the Adaptive Server Enterprise interface, PowerBuilder displays all tables in the current database.</p>
Table Owner	<p>Displays only those tables belonging to the specified table owner. You can use wildcard characters.</p> <p>If you omit this value, PowerBuilder displays all tables matching the table name that you have permission to access.</p>
Include Tables	Specifies that tables should be displayed.
Include Views	Specifies that views should be displayed.
Include System Tables	Specifies that system tables should be displayed.
Include Aliases	Specifies that alias tables should be displayed.
Include Synonyms	Specifies that synonym tables should be displayed.

*Adaptive Server Enterprise and DirectConnect* These Sybase database interfaces use stored procedures to create the table list:

- **DirectConnect interface** Uses the sp\_tables stored procedure.
- **Adaptive Server Enterprise interface** Uses the version of the sp\_pb105table stored procedure installed by you or your database administrator.

For information about which version of sp\_pb105table to install when connecting to an Adaptive Server Enterprise database, see “Installing PowerBuilder stored procedures in Adaptive Server Enterprise databases” in *Connecting to Your Database*.

PowerBuilder uses the TableCriteria parameter to supply the arguments to sp\_tables or sp\_pb105table and build the table list based on your search criteria.

**Examples** Type QADB% in the Table Name box and DWMC31 in the Table Owner box on the System tab in the Database Profile Setup dialog box to set the Table Criteria property to:

```
TableCriteria='QADB%,DWMC31'
```

## ThreadSafe

**Description** Specifies whether your connection should take advantage of the database server threadsafe client libraries.

By default, ThreadSafe is set to No to specify that your connection does not use the threadsafe client libraries. If you set ThreadSafe to Yes, your connection takes advantage of the threadsafe client libraries.

---

### When to specify ThreadSafe

You must specify a value for ThreadSafe *before* connecting to the database.

---

**Applies to** IN9 INFORMIX  
O84 Oracle 8.x and Oracle8i  
O90 Oracle9i  
O10 Oracle 10g

**Syntax** ThreadSafe='value'

Parameter	Description
<i>value</i>	Specifies whether a connection uses the database server threadsafe client libraries. Values are: <ul style="list-style-type: none"> <li>• <b>Yes</b> Your connection uses the threadsafe client libraries. Use this setting when building distributed applications that require a multi-threaded environment.</li> <li>• <b>No</b> (Default) Your connection does not use the threadsafe client libraries. Use this setting when building nondistributed applications that require a single-threaded environment.</li> </ul>

**Default value** ThreadSafe = 'No'

**Usage**                    *When to use*   Oracle and Informix provide support for thread safety in their client libraries. When you are using the Oracle or Informix database interface to build multi-threaded applications in PowerBuilder, set the ThreadSafe parameter to Yes to use threadsafe client libraries. This prevents possible side effects among multiple threads of execution making calls to the database server. Your application might incur a performance penalty when you use the threadsafe client libraries.

By default, the client software (and, thus, PowerBuilder) assumes that you are building an application in a single-threaded environment that does not need the threadsafe client libraries. This default ensures that single-threaded applications do not incur the performance penalty associated with using threadsafe libraries. Therefore, if you are building single-threaded applications, you can leave the ThreadSafe parameter set to No (the default).

This parameter cannot be set dynamically. The value set when the connection is made remains in effect until it is disconnected.

**Examples**                To specify that your connection uses the threadsafe client libraries:

- **Database profile**   Select the Thread Safe check box on the Connection tab in the Database Profile Setup dialog box.
- **Application**        Type the following in code:

```
SQLCA.DBParm = "ThreadSafe='Yes' "
```

## Time

**Description**            When you update data in the DataWindow painter, PowerBuilder builds a SQL UPDATE statement in the background. The Time parameter determines how PowerBuilder specifies a time datatype when it builds the SQL UPDATE statement.

**Applies to**             JDB JDBC  
                              ODBC  
                              O84 Oracle 8.x and Oracle8i  
                              O90 Oracle9i  
                              O10 Oracle 10g

**Syntax**                 The syntax you use to specify the Time parameter differs slightly depending on the database.

The Database Profile Setup dialog box inserts special characters (quotes and backslashes) where needed, so you can specify just the time format.

In code, you must use the following syntax:

**JDBC and ODBC syntax** PowerBuilder parses the backslash followed by two single quotes (\') as a single quote when it builds the SQL UPDATE statement:

```
Time = '\ 'time_format'
```

**Oracle syntax** PowerBuilder parses each set of four consecutive single quotes (''''') as a single quote when it builds the SQL UPDATE statement:

```
Time = ''''time_format'''''
```

Parameter	Description
'\'	<b>JDBC and ODBC syntax</b> Type a single quote, followed by one space, followed by a backslash, followed by two single quotes. There is no space between the two single quotes and the beginning of the time format.
''''''	<b>Oracle syntax</b> Type a single quote, followed by one space, followed by four single quotes. There is no space between the four single quotes and the beginning of the time format.
<i>time_format</i>	The time format you want PowerBuilder to use when it builds a SQL UPDATE statement to update a data source in the DataWindow painter. For more on display formats, see the <i>User's Guide</i> .
'\ '''	<b>JDBC and ODBC syntax</b> Type a backslash, followed by two single quotes, followed by one space, followed by a single quote. There is no space between the end of the time format and the backslash.
'''' '''	<b>Oracle syntax</b> Type four single quotes, followed by one space, followed by a single quote. There is no space between the end of the time format and the four single quotes.

Default value

The default value for Time depends on the DBMS you are accessing:

DBMS	Date default value
JDBC	If no value is specified for the Time parameter, PowerBuilder looks for a time format in the section for your JDBC driver in the registry. If no time format is found in the registry, PowerBuilder uses the JDBC time format escape sequence.
ODBC	If no value is specified for the Time parameter, PowerBuilder looks for a time format in the section for your ODBC driver in the PBODB105 initialization file. If no time format is found in the PBODB105 initialization file, PowerBuilder uses the ODBC time format escape sequence.

DBMS	Date default value
Oracle	The default Oracle date format. For information, see your Oracle documentation.

## Examples

**About these examples** Assume you are updating a table named Workhours by setting the Start column to 08:30. This time is represented by the following PowerBuilder time format:

```
hh:mm
```

**Example 1 (JDBC and ODBC syntax)** To specify that PowerBuilder should use this format for the time datatype when it builds the SQL UPDATE statement:

- **Database profile** Type the following in the Time Format box on the Syntax tab in the Database Profile Setup dialog box:

```
hh:mm
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "Time=' \'hh:mm\' ' "
```

*What happens* PowerBuilder builds the following SQL UPDATE statement to update the table:

```
UPDATE WORKHOURS
SET START = '08:30'
```

**Example 2 (Oracle syntax)** To specify that PowerBuilder should use this format for the time datatype when it builds the SQL UPDATE statement:

- **Database profile** Type `hh:mm` in the Time Format box on the Syntax tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "Time=' \'\'\'hh:mm\'\'\' ' "
```

*What happens* PowerBuilder builds the following SQL UPDATE statement to update the table:

```
UPDATE WORKHOURS
SET START = '08:30'
```

## See also

Date  
DateTime

## TimeFormat

**Description** When you update data in the DataWindow painter, PowerBuilder builds a SQL UPDATE statement in the background. The Time parameter determines how PowerBuilder specifies a time datatype when it builds the SQL UPDATE statement.

**Applies to** ADO.NET  
OLE DB

**Syntax** `TimeFormat = 'time_format'`

Parameter	Description
<code>time_format</code>	The time format you want PowerBuilder to use when it builds a SQL UPDATE statement to update a data source in the DataWindow painter. For more on display formats, see the <i>User's Guide</i> .

**Default value** If no value is specified for the TimeFormat parameter, PowerBuilder does not use a time datatype.

**Usage** When you call stored procedures, the database server might not accept the time format built by PowerBuilder. If this occurs, you can try to use another format. For example, for Microsoft SQL Server, try this format:

```
TimeFormat = '\ \' hh:mm:ss \ ' ' '
```

**Examples** Assume you are updating a table named Workhours by setting the Start column to 08:30. This time is represented by the following PowerBuilder time format:

```
hh:mm
```

To specify that PowerBuilder should use this format for the time datatype when it builds the SQL UPDATE statement:

- **Database profile** Type the following in the Time Format box on the Syntax tab in the Database Profile Setup dialog box:

```
hh:mm
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "TimeFormat='hh:mm'"
```

*What happens* PowerBuilder builds the following SQL UPDATE statement to update the table:

```
UPDATE WORKHOURS
SET START = '08:30'
```

**See also** DateFormat  
DateTimeFormat

## Timeout

**Description** Specifies the number of seconds the interface should wait for a connection to the data provider to complete.

---

**When to specify TimeOut**

You must specify a value for TimeOut *before* connecting to the database.

---

**Applies to** ADO.NET  
OLE DB

**Syntax** **TimeOut** = *value*

Parameter	Description
<i>value</i>	The number of seconds the interface waits for a connection to complete.

**Default value** None

**Usage** The default value for the TimeOut parameter is driver-specific.

**Examples** To set the TimeOut value to wait 10 seconds for a connection to complete:

- **Database profile** Type 10 in the Timeout box on the System tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "TimeOut=10"
```

## TimeStamp

**Description** Specifies whether PowerBuilder should map DateTime and Time datatypes to the Oracle TimeStamp datatype.

**Applies to** O90 Oracle9i  
O10 Oracle 10g

**Syntax** **TimeStamp** = *value*

Parameter	Description
<i>value</i>	Specifies whether PowerBuilder should map DateTime and Time datatypes to the Oracle TimeStamp datatype. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> Map DateTime and Time datatypes to the Oracle Date datatype.</li> <li>• <b>1</b> (Default) Map DateTime and Time datatypes to the Oracle TimeStamp datatype.</li> </ul>



Default value	TimeStamp=1
Usage	<p>Oracle9<i>i</i> and later databases and the O90 and O10 interfaces support the Oracle timestamp datatype. This datatype includes the date and the time including milliseconds. The existing Oracle Date datatype does not include millisecond information. In a DataWindow object, both the Oracle Timestamp and Date datatypes are mapped to the PowerBuilder DateTime datatype, which supports millisecond information.</p> <p>If you use the O90 or O10 interface with an Oracle9<i>i</i> or higher server, DateTime and Time datatypes are mapped to the Oracle TimeStamp datatype by default. If you want DateTime and Time to be mapped to the Oracle Date datatype, set the TimeStamp database parameter to 0.</p> <p>The TimeStamp database parameter does not apply to the O84 database interface. When you use the O84 interface, the DateTime and Time datatypes are always mapped to the Oracle Date datatype.</p> <p>In PowerBuilder 8 and earlier, millisecond information was truncated when used with the Oracle Date datatype. In PowerBuilder 9.0 and later, millisecond information is not truncated. As a result, when performing multiple updates to a DateTime field that maps to a Date column, the first update succeeds, but subsequent updates fail with a “row changed between retrieve and update error.”</p> <p>If you are using the O90 or O10 interface with a database that uses only the TimeStamp datatype, PowerBuilder handles DataWindow updates correctly. If you are using the O90 or O10 interface with a database that uses only the Oracle Date datatype, set the DBParm TimeStamp to 0 to truncate millisecond information.</p> <p>If you are using a database that uses both Date and TimeStamp datatypes, you must determine which columns use each datatype, and strip the milliseconds from the Date columns using code like the following:</p> <pre style="margin-left: 40px;">datetime dt dt = datetime (date(string( today() ,"dd/mm/yyyy")), &amp; time(string ( today() ,"hh:mm:ss "))) dw_1.setitem(1,3,dt)</pre>
Examples	<p>To set the TimeStamp value to treat DateTime and Time DataWindow datatypes as Oracle Date datatypes:</p> <ul style="list-style-type: none"> <li>• <b>Database profile</b> Clear the Map DateTime/Time to Oracle Timestamp check box on the Syntax page in the Database Profile Setup dialog box.</li> </ul>

- **Application** Type the following in code:

```
SQLCA.DBParm = "TimeStamp=0"
```

## TraceFile

**Description** Specifies that the JDBC Driver Manager Trace tool should trace a connection to the database you access through the PowerBuilder JDBC interface.

**Applies to** JDB JDBC

**Syntax** **TraceFile** = 'tracefile\_name'

**Default value** None

**Usage** The JDBC Driver Manager Trace logs errors and informational messages originating from the Driver object currently loaded (such as the Sybase jConnect JDBC driver) when PowerBuilder connects to a database through the JDBC interface. It writes this information to a log file (default is JDBC.LOG) or to a file you specify. The amount of trace output varies depending on the JDBC driver being used.

You can start and stop the JDBC Driver Manager Trace in the PowerBuilder development environment by editing the database profile for the connection you want to trace. You can also start and stop the JDBC Driver Manager Trace in a PowerBuilder application by specifying the TraceFile parameter in the appropriate script.

For more information about using the JDBC Driver Manager Trace tool, see *Connecting to Your Database*.

**Examples** To start the JDBC Driver Manager Trace and specify a log file:

- **Database profile** Select the Trace JDBC Calls check box and type the following in the Trace File box on the Options tab in the Database Profile Setup dialog box:

```
c:\temp\jdbctrce.log
```

- **Application** Type the following in code:

```
SQLCA.DBParm = "TraceFile='c:\temp\jdbctrce.log'"
```

## TrimSpaces

**Description** Specifies whether PowerBuilder should trim trailing spaces from data values retrieved from the following datatypes: Char, Char for Bit Data, VarChar, and VarChar for Bit Data.

**Applies to** ADO.NET  
DIR Sybase DirectConnect  
JDB JDBC  
ODBC  
SYC and SYJ Sybase Adaptive Server Enterprise

**Syntax** **TrimSpaces** = *value*

Parameter	Description
<i>value</i>	Specifies whether PowerBuilder should trim trailing spaces from data of type Char, Char for Bit Data, and VarChar for Bit Data. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> Do not trim trailing spaces.</li> <li>• <b>1</b> (Default) Trim trailing spaces.</li> </ul>

**Default value** TrimSpaces=0 (ADO.NET) or TrimSpaces=1 (DIR and SYC). For JDBC, the default values depend on the PBTrimCharColumns value in the registry. For ODBC, the default values depend on the PBTrimCharColumns value in the PBODB*nmn*.INI file. (If the PBTrimCharColumns keyword is missing for a particular database connection, the default value for the ODBC interface is TrimSpaces=0.)

**Usage** By default, PowerBuilder trims spaces from the following datatypes: Char, Char for Bit Data, VarChar, and VarChar for Bit Data.

---

### ODBC database interface

Some ODBC drivers, such as ASA, trim trailing spaces before the data reaches the fetch buffer—even when TrimSpaces is set to 0.

---

If your DBMS makes a distinction between Char data with trailing spaces and Char data without trailing spaces when evaluating a WHERE clause expression, you might receive the message Row changed between retrieve and update when your DataWindow update properties are set to “Key and updateable columns.” To prevent this, change your DataWindow update properties. In embedded SQL, you can check Sqlca.Sqlnrows after each update to determine if the update took place. Avoid using Char data columns in the WHERE clause of an UPDATE or DELETE statement when TrimSpaces=1.

Examples

To specify that PowerBuilder should not trim trailing spaces:

- **Database profile** Clear the Trim Trailing Spaces In CHAR Data check box on the Syntax tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "TrimSpaces=0"
```

## TrustedConnection

Description

Specifies whether the current Windows account credentials can be used for authentication.

---

### When to specify TrustedConnection

You must specify the TrustedConnection parameter *before* connecting to the database.

---

Applies to

ADO.NET

Syntax

**TrustedConnection** = *value*

Parameter	Description
<i>value</i>	Specifies whether the current Windows account credentials can be used for authentication. Values are: <ul style="list-style-type: none"><li>• <b>0</b> (Default) The User ID and Password are specified in the connection.</li><li>• <b>1</b> The current Windows account credentials are used for authentication. The User ID and Password supplied in the connection are ignored.</li></ul>

Default value

TrustedConnection = 0

Examples

To specify that PowerBuilder should trust the connection:

- **Database profile** Select the Trusted Connection check box on the General tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "TrustedConnection=1"
```

## TRS

**Description** Specifies whether you want your application to connect to a database through the DirectConnect server using:

- DirectConnect Access Service for DB2/MVS
- DirectConnect TRS
- Gatewayless connection using OpenServerConnect

**Applies to** DIR Sybase DirectConnect

**Syntax** **TRS** = *value*

Parameter	Description
<i>value</i>	Specifies how your application should connect to a database through the DirectConnect server. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Use an Access Service connection.</li> <li>• <b>1</b> Use a TRS connection.</li> <li>• <b>2</b> Use a gatewayless or OpenServerConnect connection.</li> </ul>

**Default value** TRS = 0

**Usage** If you have chosen to make a gatewayless database connection, you can then set the UseProcSyntax parameter to specify whether PowerBuilder should convert the syntax for invoking a Remote Stored Procedure (RSP) or host-resident request before executing that procedure.

**Examples** To specify that you want to connect to a database using OpenServerConnect:

- **Database profile** Select Gatewayless from the Choose Gateway drop-down list on the Connection tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "TRS=2"
```

**See also** UseProcSyntax  
HostReqOwner

## URL

**Description** The location of the database to which you want to connect using the JDBC interface.

---

### When to specify URL

You must specify the URL parameter *before* connecting to the database.

---

Applies to JDB JDBC

Syntax **URL = 'URL\_address'**

Default value None

Usage The database URL is obtained from the database JDBC driver documentation. A list of registered Driver classes, with their URLs, is maintained by the driver's JDBC DriverManager class. When a connection request is made, the DriverManager attempts to locate a suitable driver from those listed.

The URL uses this general format:

*jdbc:vendor.driverprotocol:servername:port/database*

Argument	Description
<i>jdbc</i>	Driver
<i>vendor</i>	Database vendor (such as Sybase or Oracle)
<i>driverprotocol</i>	Database communications protocol
<i>servername</i>	DNS machine name or database host name
<i>port</i>	TCP/IP port number configured for accessing the database server
<i>database</i>	(optional) Name of a specific database

The database URL can also include the user ID and password as follows:

*jdbc:vendor.driverprotocol.userid/password@servername:port.database*

Examples

**Example 1** To set the URL to a database accessed through jConnect:

- **Database profile** Type the following in the URL box on the Connection tab in the Database Profile Setup dialog box:

```
jdbc:sybase:Tds:199.93.178.151:5007/tsdata
```

- **Application** Type the following in code:

```
SQLCA.DBParm =
"URL='jdbc:sybase:Tds:199.93.178.151:5007/tsdata'"
```

**Example 2** To set the URL to a database accessed through the Oracle JDBC driver:

- **Database profile** Type the following in the URL box on the Connection tab in the Database Profile Setup dialog box:

```
jdbc:oracle:thin:@ora80nt:1521:orcl
```

- **Application** Type the following in code:

```
SQLCA.DBParm =
"URL='jdbc:oracle:thin:@ora80nt:1521:orcl'"
```

**Example 3** To set the URL, which includes the user ID and password, to a database accessed through the Oracle JDBC driver:

- **Database profile** Type the following in the URL box on the Connection tab in the Database Profile Setup dialog box:

```
jdbc:oracle:thin:system/manager@ora80nt:1521:orcl
```

- **Application** Type the following in code:

```
SQLCA.DBParm =
"URL='jdbc:oracle:thin:system/manager@ora80nt:1521:
orcl'"
```

See also

Driver

## UseContextObject

**Description** Specifies that PowerBuilder controls a transaction using the transaction service context object TransactionServer. This parameter applies *only* when a PowerBuilder custom class user object is deployed as an EAServer or COM+ component.

**Applies to** JDB JDBC  
 ODBC  
 O84 Oracle 8.x and Oracle8i  
 O90 Oracle9i  
 SYJ Sybase Adaptive Server Enterprise

---

### Database interface restrictions

**EAServer requires the SYJ interface** Sybase EAServer uses a slightly different version of the CT-Lib software. Therefore, *at runtime*, you need to use the SYJ database interface rather than SYC to connect to an Adaptive Server Enterprise database. The SYJ Database Profile Setup dialog box provides a convenient way to set the appropriate connection parameters and then copy the syntax from the Preview tab into the script for your Transaction object.

You cannot use the SYJ interface, however, to connect to the database in the PowerBuilder development environment. Therefore, *during the development phase* (before the component has been deployed to EAServer), you must use SYC to connect to the database.

---

**Syntax** `UseContextObject = 'value'`

**Default value** UseContextObject = No

Usage	<p>PowerBuilder provides a transaction service context object called TransactionServer that gives you access to the transaction state primitives that influence whether EAServer or COM+ commits or aborts the current transaction. If you use the TransactionServer context object by setting the UseContextObject parameter to Yes, COMMIT and ROLLBACK statements called on the Transaction object result in a runtime error.</p> <p>By default, the TransactionServer context object is not used. Instead, you can use COMMIT and ROLLBACK statements to manage transactions. In this case, COMMIT is interpreted as a SetComplete function and ROLLBACK is interpreted as a SetAbort function. This approach is recommended only when you want to migrate PowerBuilder 6.x or prior objects to EAServer or COM+ without modifying the code.</p> <p>Setting UseContextObject to Yes is incompatible with the use of the SetTrans function. The SetTrans function is used when you want the DataWindow engine to manage database connections, transaction state primitives, and related EAServer component deactivation.</p> <p>Because the default Web DataWindow component uses SetTrans to specify database connection information, you must not set UseContextObject to Yes in your database profile or in the EAServer properties for the component.</p> <p>For information on how to use PowerBuilder to build EAServer and COM+ components, see <i>Application Techniques</i>.</p>
Examples	<p>To use the TransactionServer context object:</p> <ul style="list-style-type: none"><li>• <b>Database profile</b> Select the Use Transaction Context Object check box on the EAServer or EAServer/COM+ tab in the Database Profile Setup dialog box.</li><li>• <b>Application</b> Type the following in code:<pre>SQLCA.DBParm = "UseContextObject = 'Yes'"</pre></li></ul>
See also	<p>CacheName GetConnectionOption ReleaseConnectionOption</p>



## UseProcSyntax

**Description** Specifies whether PowerBuilder should convert the syntax for invoking a Remote Stored Procedure (RSP) or host-resident request before executing that procedure.

**Applies to** DIR Sybase DirectConnect (applies only to Open ServerConnect)

**Syntax** **UseProcSyntax** = *value*

Parameter	Description
<i>value</i>	Specifies whether PowerBuilder should convert RSP or host-resident request syntax. Values are: <ul style="list-style-type: none"> <li>• <b>0</b> (Default) Do not convert syntax.</li> <li>• <b>1</b> Convert syntax to USE PROCEDURE.</li> </ul>

**Default value** UseProcSyntax = 0

**Usage** UseProcSyntax applies *only* if you are using Open ServerConnect to make a gatewayless database connection to a DB2/MVS database. To indicate that you want to use Open ServerConnect, select Gatewayless from the Choose Gateway drop-down list on the Connection tab. If you select Gatewayless, and set the UseProcSyntax parameter to 1, PowerBuilder converts the EXECUTE procedure syntax it normally uses to the USE PROCEDURE syntax required to invoke RSP and host-resident requests.

**Examples** To specify that PowerBuilder should convert RSP or host-resident syntax:

- **Database profile** Select the Use Procedure Syntax for RSPs check box on the Syntax tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "UseProcSyntax=1;TRS=2"
```

**See also** TRS  
HostReqOwner

## UTF8

**Description** The UTF8 database parameter specifies whether the database server you are accessing will handle conversion between the character sets on the client and server when they are different.

**When to specify UTF8**

You must specify a value for UTF8 *before* connecting to the database in PowerBuilder.

---

Applies to

DIR Sybase DirectConnect  
 SYC and SYJ Sybase Adaptive Server Enterprise

Syntax

**UTF8** = *value*

Parameter	Description
<i>value</i>	<p>Specifies whether the database server you are accessing will perform conversion between the character sets used on the client and server. Values are:</p> <ul style="list-style-type: none"> <li><b>0</b> (Default) The PowerBuilder database interface performs the conversion. Multiple languages are not supported.</li> <li><b>1</b> Your database server performs the conversion. Multiple languages are supported.</li> </ul>

Default value

UTF8 = 0

Usage

If UTF8 is set to 1, PowerBuilder always uses UTF-8 as the client character set when connecting to an Adaptive Server database. When UTF8 is set to 0, if the client and database server character sets are different, the database interface converts Transact-SQL, identifiers, parameters, and Char and VarChar data to and from the character set used on the server. Multiple languages are not supported with this setting.

To enable multilanguage support, you must set the UTF8 database parameter to 1 and the database server must have the UTF-8 character set installed, or, for Adaptive Server, it must be configured to support Unicode conversions. To do so, the database administrator must run the following command on the server:

```
sp_configure "enable Unicode conversion", 2
```

This enables the server to perform the conversion to and from Unicode.

Examples

To specify that the database server you are accessing with PowerBuilder uses UTF-8 as its default character set:

- **Database profile** Select the UTF8 Character Set Installed or Unicode Conversion Enabled check box on the Regional Settings tab in the Database Profile Setup dialog box.
- **Application** Type the following in code:

```
SQLCA.DBParm = "UTF8=1"
```

About this chapter

This chapter describes the syntax and use of each connection-related database preference that you can set in PowerBuilder.

Contents

The database preferences are listed in alphabetical order.

## Database preferences and supported database interfaces

The following table lists each supported database interface and the connection-related database preferences you can use with that interface in PowerBuilder. The preferences listed in the table pertain to the database connection, and not to the behavior of the Database painter itself.

<b>Database interface</b>	<b>Database preferences</b>
ADO.NET	AutoCommit Connect to Default Profile Keep Connection Open Read Only Shared Database Profiles SQL Terminator Character Use Extended Attributes
DIR Sybase DirectConnect	AutoCommit Connect to Default Profile Keep Connection Open Lock Read Only Shared Database Profiles SQL Terminator Character Use Extended Attributes

Database interface	Database preferences
IN9 Informix	AutoCommit Connect to Default Profile Keep Connection Open Lock Read Only Shared Database Profiles SQL Terminator Character Use Extended Attributes
JDBC	AutoCommit Connect to Default Profile Keep Connection Open Lock Read Only Shared Database Profiles SQL Terminator Character Use Extended Attributes
ODBC  <hr/> <b>Using AutoCommit and Lock with ODBC</b> The AutoCommit and Lock database preferences are supported by the ODBC interface only if <i>both</i> the ODBC driver you are using and the back-end DBMS support the feature.	AutoCommit Connect to Default Profile Keep Connection Open Lock Read Only Shared Database Profiles SQL Terminator Character Use Extended Attributes
OLE DB	AutoCommit Connect to Default Profile Keep Connection Open Read Only Shared Database Profiles SQL Terminator Character Use Extended Attributes
O84 Oracle 8.x.and Oracle8i O90 Oracle9i O10 Oracle 10g	Connect to Default Profile Keep Connection Open Read Only Shared Database Profiles SQL Terminator Character Use Extended Attributes

Database interface	Database preferences
SYC Sybase Adaptive Server Enterprise	AutoCommit Connect to Default Profile Keep Connection Open Lock Read Only Shared Database Profiles SQL Terminator Character Use Extended Attributes
SYJ Sybase Adaptive Server Enterprise	AutoCommit Connect to Default Profile Keep Connection Open Lock Read Only Shared Database Profiles SQL Terminator Character Use Extended Attributes

## AutoCommit

### Description

For those DBMSs and database interfaces that support it, AutoCommit controls whether PowerBuilder issues SQL statements outside or inside the scope of a transaction.

When AutoCommit is set to False (the default), PowerBuilder issues SQL statements *inside* the scope of a transaction. When AutoCommit is set to True, PowerBuilder issues SQL statements *outside* the scope of a transaction.

### When to specify AutoCommit

*In the development environment*, you must set AutoCommit before connecting to the database. AutoCommit takes effect only when the database connection occurs. Changes to AutoCommit after the connection occurs have no effect on the current connection.

*In code*, you can reset the value of AutoCommit at any time. This lets you override the initial setting if necessary.

### Applies to

ADO.NET  
 DIR Sybase DirectConnect  
 IN9 Informix  
 JDB JDBC  
 ODBC (if driver and back-end DBMS support this feature)

OLE DB  
 SYC and SYJ Sybase Adaptive Server Enterprise

In an application

For those DBMSs and database interfaces that support it, you can set AutoCommit in a script as a property of the Transaction object. The following syntax assumes you are using the default Transaction object SQLCA (but you can also define your own Transaction object):

**SQLCA.AutoCommit** = *value*

Parameter	Description
<i>value</i>	<p>Specifies whether PowerBuilder issues SQL statements outside or inside the scope of a transaction. Values are:</p> <ul style="list-style-type: none"> <li>• <b>True</b> PowerBuilder issues SQL statements <i>outside the scope of a transaction</i>. The statements are not part of a logical unit of work (LUW). If the SQL statement is successful, the DBMS updates the database immediately as if a COMMIT statement had been issued.</li> <li>• <b>False</b> (Default) PowerBuilder issues SQL statements <i>inside the scope of a transaction</i>. PowerBuilder issues a BEGIN TRANSACTION statement at the start of the connection and issues another BEGIN TRANSACTION statement after each COMMIT or ROLLBACK statement is issued.</li> </ul>

In the development environment

Select or clear the AutoCommit Mode check box on the Connection tab in the Database Profile Setup dialog box, as follows:

- **Select the check box** Sets AutoCommit to true for this connection.
- **Clear the check box** (Default) Sets AutoCommit to false for this connection.

For instructions, see “Setting Additional Connection Parameters” in *Connecting to Your Database*.

Default value

AutoCommit = False

Usage

*Transactions* A **transaction** is one or more SQL statements that form a **logical unit of work (LUW)**. Within a transaction, all SQL statements must succeed or fail as one logical entity. Changes are made to the database only if all statements in the transaction succeed and a COMMIT is issued. If one or more statements fail, you must issue a ROLLBACK to undo the changes. This ensures the integrity and security of data in your database.

*Executing SQL DDL statements* Some DBMSs require you to execute certain SQL statements outside the scope of a transaction. For example, when connected to a SQL Server database, you must execute SQL Data Definition Language (DDL) statements such as CREATE TABLE and DROP TABLE outside a transaction. There are two reasons for this:

- It ensures that the structure of your database cannot change during a transaction.
- It improves database performance, because DDL statements are costly operations to recover.

Therefore, to execute DDL statements or stored procedures containing DDL statements in a SQL Server database, you must set AutoCommit to true to issue the DDL statements outside the scope of a transaction. You should, however, set AutoCommit back to false immediately after executing the DDL statements.

When you change the value of AutoCommit from false to true, PowerBuilder issues a COMMIT statement by default.

---

**Caution**

When you set AutoCommit to true, you cannot roll back database changes. Therefore, use care when changing the setting of AutoCommit.

---

*Using EXECUTE IMMEDIATE* When AutoCommit is set to True, you can use the EXECUTE IMMEDIATE dynamic SQL statement to issue BEGIN TRANSACTION, COMMIT TRANSACTION, ROLLBACK TRANSACTION, and other SQL statements to control your own transaction processing. If you use the EXECUTE IMMEDIATE dynamic SQL statement to issue BEGIN TRANSACTION, you must use the EXECUTE IMMEDIATE dynamic SQL statement to issue a corresponding COMMIT TRANSACTION or ROLLBACK TRANSACTION.

For information about using the EXECUTE IMMEDIATE statement, see the *PowerScript Reference*.

*DirectConnect interface* As part of the Connect process, the DIR interface automatically issues TransactionMode = short to override the access service default configuration. It then issues begin transaction at connect time and after every Commit and Rollback whenever AutoCommit = False. Most developers should start their connections with AutoCommit = True, switch to False only when the application demands transaction processing, and then switch back to AutoCommit = True after the transaction is committed or rolled back.

Examples	<p>To set AutoCommit to true and issue SQL statements outside the scope of a transaction:</p> <ul style="list-style-type: none"><li>• <b>Development environment</b> Select the AutoCommit Mode check box on the Connection tab in the Database Profile Setup dialog box.</li><li>• <b>Application</b> Type the following in a script: <pre>SQLCA.AutoCommit = True</pre></li></ul> <p><b>Using the examples in code</b> If you specify AutoCommit Mode in your database profile, the correct syntax displays on the Preview tab in the Database Profile Setup dialog box. You can copy the syntax from the Preview tab into your code.</p>
----------	---

## Connect to Default Profile

Description	Connect to Default Profile controls whether the Database painter establishes a connection to a database using a default profile when the painter is invoked. If not selected, the Database painter opens without establishing a connection to a database.
Applies to	All database interfaces
In an application	You <i>cannot</i> set the Connect to Default Profile database preference in code.
In the development environment	<p>In the Database painter, select or clear the Connect to Default Profile check box in the Database Preferences property sheet as follows:</p> <ul style="list-style-type: none"><li>• <b>Select the check box</b> (Default) The next time you invoke the Database painter, it automatically connects to the default database profile.</li><li>• <b>Clear the check box</b> The next time you invoke the Database painter, it does <i>not</i> automatically connect to the default database profile.</li></ul>
Default value	The Connect to Default Profile check box in the Database Preferences property sheet is selected by default.
Usage	Connect to Default Profile allows you to open the Database painter <i>without</i> establishing a connection to a database. Consequently, you can perform all database-related tasks, including defining a database profile and connecting to a database, in the Database painter. However, you might want to continue to define profiles and/or connect to a database using the Database Profile since opening the Database painter uses more system resources.



## Keep Connection Open

Description	<p>By default, PowerBuilder opens a database connection the first time you open a painter requiring a connection, and stays connected throughout the session until you exit.</p> <p>When you connect to a database in the PowerBuilder development environment without using a database profile, you can set the Keep Connection Open database preference to specify when PowerBuilder closes the database connection.</p> <p>Keep Connection Open applies only when connecting to a database in the PowerBuilder development environment without using a database profile. The setting of Keep Connection Open has no effect when you use a database profile to connect in PowerBuilder.</p>
Applies to	All database interfaces (only in the development environment)
In an application	You <i>cannot</i> set the Keep Connection Open database preference in code.
In the development environment	<p>In the Database painter, select or clear the Keep Connection Open check box in the Database Preferences property sheet as follows:</p> <ul style="list-style-type: none"> <li>• <b>Select the check box</b> (Default) Stays connected to the database throughout your PowerBuilder session and closes the connection when you exit.</li> <li>• <b>Clear the check box</b> Opens the database connection when a painter requires it and closes the connection when you close a painter or finish compiling a script</li> </ul>
Default value	The Keep Connection Open check box in the Database Preferences property sheet is selected by default.
Usage	<p><i>Requirements for using Keep Connection Open</i> To use the Keep Connection Open database preference, <i>both</i> of the following must be true:</p> <ul style="list-style-type: none"> <li>• <b>Working in the development environment</b> You must be working in the development environment.</li> <li>• <b>Using default connection information</b> PowerBuilder must use the most recently used connection information in the Windows registry to connect to the database. Keep Connection Open has no effect when you select a database profile to connect to the database.</li> </ul>

*What happens* If you meet both of these requirements, clearing the Keep Connection Open check box opens a database connection only when you are working in a painter that requires a connection, and closes the connection at other times. This can save you money if you are accessing a database that charges for connect time.

## Lock

### Description

For those DBMSs and database interfaces that support the use of lock values and isolation levels, the Lock preference sets the isolation level to use when connecting to the database.

In multiuser databases, transactions initiated by different users can overlap. If these transactions access common data in the database, they can overwrite each other or collide.

To prevent concurrent transactions from interfering with each other and compromising the integrity of your database, certain DBMSs allow you to set the isolation level when you connect to the database. **Isolation levels** are defined by your DBMS, and specify the degree to which operations in one transaction are visible to operations in a concurrent transaction. Isolation levels determine how your DBMS isolates or **locks** data from other processes while it is being accessed.

PowerBuilder uses the Lock preference to allow you to set various database lock options. Each lock value corresponds to an isolation level defined by your DBMS.

---

### When to specify the Lock value

You must set the Lock value *before* you connect to the database. The Lock value takes effect only when the database connection occurs. Changes to the Lock value after the connection occurs have no effect on the current connection.

---

### Applies to

DIR Sybase DirectConnect  
IN9 Informix (OnLine databases)  
JDB JDBC  
ODBC (if driver and back-end DBMS support this feature)  
OLE DB  
SYC and SYJ Sybase Adaptive Server Enterprise

In an application For those DBMSs and database interfaces that support it, you can set the Lock value in code as a property of the Transaction object. The following syntax assumes you are using the default Transaction object, SQLCA, but you can also use a user-defined Transaction object:

**SQLCA.Lock = 'value'**

where *value* is the lock value you want to set.

Lock values The following table lists the lock values and corresponding isolation levels for each database interface that supports locking. You set the lock value in code, and the isolation level in a database profile.

For more about the isolation levels that your DBMS supports, see your DBMS documentation.

Database interface	Lock values	Isolation levels
IN9 Informix (for OnLine databases only)	Dirty Read	Dirty Read
	Committed Read	Committed Read
	Cursor Stability	Cursor Stability
	Repeatable Read	Repeatable Read
JDB JDBC	RU	Read Uncommitted
	RC	Read Committed
	RR	Repeatable Read
	TS	Serializable Transactions
	TN	Transaction None
ODBC	RU	Read Uncommitted
	RC	Read Committed
	RR	Repeatable Read
	TS	Serializable Transactions
	TV	Transaction Versioning
OLE DB	RU	Read Uncommitted
	RC	Read Committed
	RR	Repeatable Read
	TS	Serializable Transactions (default)
	TC	Chaos
Sybase Adaptive Server Enterprise	0	Read Uncommitted
	1	Read Committed (default)
	3	Serializable Transactions

Database interface	Lock values	Isolation levels
Sybase DirectConnect	0	Read Uncommitted
	1	Read Committed (default)
	2	Repeatable Read
	3	Serializable Transactions

In the development environment

Select the isolation level you want from the Isolation Level drop-down list on the Connection tab in the Database Profile Setup dialog box.

For instructions, see “Setting Additional Connection Parameters” in *Connecting to Your Database*.

Default value

The default lock value depends on how your database is configured. For information, see your DBMS documentation.

Usage

*ODBC* The TV (Transaction Versioning) setting does *not* apply to Adaptive Server Anywhere databases.

*OLE DB* Support for the MSS native driver for Microsoft SQL Server was discontinued in PowerBuilder because Microsoft discontinued support for the underlying DBLib interface in Microsoft SQL Server 2000. Microsoft recommended the use of OLE DB instead. The default value for Lock in the MSS interface was Read Committed, but for OLE DB the default is Serializable Transactions. You can override the default value by specifying a value for Lock in the *PBODB105.INI* file. For example:

```
[Microsoft SQL Server]
...
LOCK= 'RC'
...
```

The value in the *PBODB105.INI* file is used if you do not change the default in the database profile or set the Lock parameter of the Transaction object in code.

*Sybase Adaptive Server Enterprise* Sybase Adaptive Server Enterprise supports the following lock values, which correspond to SQL Server isolation levels:

- **0—Read Uncommitted (dirty reads)** Isolation level 0 prevents other transactions from changing data that an uncommitted transaction has already modified (through SQL statements such as UPDATE).

Other transactions cannot modify the data until the transaction commits, but they can still read the uncommitted data (perform dirty reads). Isolation level 0 prohibits retrieval locks on tables or pages.

Isolation level 0 is valid only for Sybase System 10 or higher databases.

- **1—Read Committed** (Default) Isolation level 1 prevents dirty reads by issuing shared locks on tables or pages.

A **dirty read** occurs when one transaction modifies a table row and a second transaction reads that row before the first transaction commits the change. If the first transaction rolls back the change, the information read by the second transaction becomes invalid.

- **3—Serializable Transactions (HOLDLOCK behavior)** Isolation level 3 prevents dirty reads, nonrepeatable reads, and phantoms for the duration of a transaction.

A **nonrepeatable read** occurs when one transaction reads a row and then a second transaction modifies that row. If the second transaction commits the change, subsequent reads by the first transaction produce different results than the original read.

A **phantom** occurs when one transaction reads a set of rows that satisfy a search condition, and then a second transaction modifies that data through a SQL INSERT, UPDATE, or DELETE statement. Subsequent reads by the first transaction using the same search conditions produce a different set of rows than the original read.

*Dynamically controlling the isolation level* PowerBuilder makes a second connection to implement either of the following while connected to a Sybase Adaptive Server Enterprise database:

- The Retrieve.AsNeeded property to specify that a DataWindow should retrieve only as many rows as needed from the database
- A SELECTBLOB embedded SQL statement to select a single blob column in a specified table row

The lock value you set before making the first Adaptive Server Enterprise connection is automatically inherited by the second connection, and *cannot be changed for the second connection*.

However, you can dynamically control the isolation level for the first (original) Adaptive Server Enterprise connection in an application by coding the following PowerScript embedded SQL statement, where *n* is 0, 1, or 3 for the isolation level you want to set for the first connection:

```
EXECUTE IMMEDIATE "set transaction isolation level n"
```

For example, the following PowerScript embedded SQL code specifies isolation level 0 (dirty read behavior) for the second connection, and isolation level 1 (read committed behavior) for the first connection:

```
// Isolation level inherited by second connection
SQLCA.Lock = "0"
CONNECT USING SQLCA;
// Override lock value 0 for first connection only
EXECUTE IMMEDIATE "set transaction isolation level 1";
```

### Examples

**Example 1** To set the Lock value to RC (Read Committed) for an Adaptive Server Anywhere database:

- **Development environment** Select Read Committed from the Isolation Level drop-down list in the Database Profile Setup dialog box.
- **Application** Type the following in a script:

```
SQLCA.Lock="RC"
```

**Example 2** To set the Lock value to 3 (Serializable Transactions) for a Sybase Adaptive Server Enterprise database:

- **Development environment** Select Serializable Transactions from the Isolation Level drop-down list in the Database Profile Setup dialog box.
- **Application** Type the following in a script:

```
SQLCA.Lock=" 3"
```

**Using the examples in code** If you specify Isolation Level in your database profile, the syntax displays on the Preview tab in the Database Profile Setup dialog box. You can copy the syntax from the Preview tab into your code.

## Read Only

### Description

Read Only specifies whether PowerBuilder should update the extended attribute system tables and any other tables in your database. The extended attribute system tables (also known as the extended catalog) consist of five tables that contain default extended attribute information for your database.

The Read Only setting determines whether you can modify (update) the tables in your database. By default, the Read Only check box is cleared in the Database Preferences property sheet. This means that PowerBuilder updates the extended attribute system tables and other tables in your database when you make changes.

If you select the Read Only check box, PowerBuilder *does not update* the extended attribute system tables or any other tables in your database. You *cannot* modify (update) information in the extended attribute system tables or any other database tables from the DataWindow painter when the Read Only check box is selected.

Applies to	All database interfaces
In an application	You <i>cannot</i> set the Read Only database preference in code.
In the development environment	In the Database painter, select or clear the Read Only check box in the Database Preferences property sheet as follows: <ul style="list-style-type: none"> <li>• <b>Select the check box</b> PowerBuilder does not update the extended attribute system tables or any other tables in your database. You <i>cannot</i> modify (update) information in the extended attribute system tables or any other database tables from the DataWindow painter when the Read Only check box is selected.</li> <li>• <b>Clear the check box</b> (Default) PowerBuilder updates the extended attribute system tables and any other tables in your database when you modify them.</li> </ul>
Default value	The Read Only check box in the Database Preferences property sheet is cleared by default.
Usage	If you select the Read Only check box in the Database Preferences property sheet, you cannot modify information in <i>any</i> tables from the DataWindow painter.  Therefore, you can use only: <ul style="list-style-type: none"> <li>• SELECT and Retrieve statements in the DataWindow and Report painters</li> <li>• SELECT statements in embedded SQL</li> </ul>
See also	Use Extended Attributes

## Shared Database Profiles

Description	Specifies the path name of the PowerBuilder initialization file containing the database profiles you want to share.  For instructions on sharing database profiles in the PowerBuilder development environment, see “Managing Database Connections” in <i>Connecting to Your Database</i> .
Applies to	All database interfaces

In an application	You <i>cannot</i> set the Shared Database Profiles database preference in code.
In the development environment	<p>In the Database painter, supply the path name of the PowerBuilder initialization file containing shared profiles in the Shared Database Profiles box in the Database Preferences property sheet. You can type the path name or click the Browse button to display it.</p> <p>For instructions, see “Setting Additional Connection Parameters” in <i>Connecting to Your Database</i>.</p>
Default value	The Shared Database Profiles box in the Database Preferences property sheet is blank (unspecified) by default.
Examples	<p>To share database profiles contained in the file <code>I:\SHARE\PB.INI</code> on the Windows platform, type or browse to the following in the Shared Database Profiles box in the Database Preferences property sheet:</p> <pre>I : \SHARE\PB . INI</pre>

## SQL Terminator Character

Description	<p>Specifies the SQL statement terminator character used by the Database painter’s Interactive SQL (ISQL) view.</p> <p>The default terminator character for the ISQL view is a semicolon (;). If a semicolon conflicts with the terminator character used by your DBMS syntax, you can change the painter’s terminator character by specifying a different character in the SQL Terminator Character box in the Database Preferences property sheet. A good choice for a terminator character is the backquote ( ` ) character.</p> <p>Changing the terminator character is recommended when you are using the ISQL view to create or execute stored procedures, triggers, and SQL scripts.</p>
Applies to	All database interfaces
In an application	You <i>cannot</i> set the SQL Terminator Character database preference in code.
In the development environment	In the Database Preferences property sheet in the Database painter, type the terminator character you want to use in the SQL Terminator Character box. For instructions, see “Setting Additional Connection Parameters” in <i>Connecting to Your Database</i> .
Default value	The default SQL Terminator Character value in the Database Preferences property sheet is a semicolon (;).



Usage	<p>The following are typical situations that might require you to change the default SQL Terminator Character value:</p> <ul style="list-style-type: none"> <li>• <b>Creating stored procedures and triggers</b> If you are creating stored procedures and triggers in the ISQL view, change the painter's terminator character to one that you do not expect to use in the stored procedure or trigger syntax for your DBMS, such as the backquote ( ` ) character.</li> </ul> <p>After you finish using the stored procedure, you can change the terminator character back to a semicolon (;). If you prefer, you can continue to use the new terminator character as long as it does not conflict with any stored procedure or trigger syntax you plan to use.</p> <ul style="list-style-type: none"> <li>• <b>Executing SQL scripts</b> If you plan to execute any SQL scripts in the ISQL view, make sure the terminator character used in the script agrees with the terminator character currently set in the view.</li> </ul>
Examples	<p>To change the SQL statement terminator character in the ISQL view to a backquote ( ` ), type a backquote in the SQL Terminator Character box in the Database Preferences property sheet.</p>

## Use Extended Attributes

Description	<p>Controls access to the extended attribute system tables by specifying whether you want PowerBuilder to create these tables. The extended attribute system tables (also known as the extended catalog) consist of five tables that contain default extended attribute information for your database.</p> <p>By default, the Use Extended Attributes check box is selected in the Database Preferences property sheet. This setting creates the extended attribute system tables the first time you connect to a database using PowerBuilder.</p>
Applies to	All database interfaces
In an application	You <i>cannot</i> set the Use Extended Attributes database preference in code.

In the development environment	<p>In the Database painter, select or clear the Use Extended Attributes check box in the Database Preferences property sheet as follows:</p> <ul style="list-style-type: none"><li>• <b>Select the check box</b> (Default) Creates the extended attribute system tables when connecting to the database for the first time.</li><li>• <b>Clear the check box</b> Does <i>not</i> create the extended attribute system tables if they do not exist. Instead, the DataWindow painter use the appropriate default values for extended attributes (such as headers, labels, and text color). If the extended attribute system tables already exist, PowerBuilder does not use them when you create a new DataWindow object.</li></ul>
Default value	<p>The Use Extended Attributes check box in the Database Preferences property sheet is selected by default.</p>
Usage	<p>If you clear the Use Extended Attributes check box in the Database Preferences property sheet, PowerBuilder <i>does not do</i> any of the following:</p> <ul style="list-style-type: none"><li>• Create the extended attribute system tables</li><li>• Insert, update, or delete rows in the extended attribute system tables</li><li>• Select information (such as header names) from the extended attribute system tables</li><li>• Execute statements that reference the extended attribute system tables</li></ul>
See also	<p>Read Only</p>

# Index

## A

ADORElease database parameter 6  
AppName database parameter 7  
Async database parameter 8  
asynchronous operations, enabling 8  
authentication information, saving in OLE DB databases 132  
authentication service, specifying in OLE DB databases 94  
AutoCommit database preference 205  
AutoCommit Mode check box in Database Profile Setup dialog box 205  
AutoCommit transaction object property 205

## B

backquote (‘), as SQL terminator character 216  
bind variables  
    and cached SQL statements 57, 177  
    and default column values 57  
    disabling default binding 56  
    using in SQL statements 56  
BindSPInput database parameter 10  
BinTxtBlob database parameter 11  
Block database parameter  
    ODBC 13  
    OLE DB 13  
    Oracle 13  
    Sybase Adaptive Server Enterprise 15  
    Sybase DirectConnect 15  
blocking factor, setting for cursors 13, 15

## C

CacheAuthentication database parameter 16  
CacheName database parameter 16

caching SQL statements  
    about 176  
    with bind variables 57, 177  
caching SQL statements with bind variables 177  
CallEscape database parameter 18  
case sensitivity, in Oracle databases 107  
catalogs, DB2 shadow 183  
CDB value, in ODBC connect string 28  
character set, setting 19  
CharSet database parameter 19  
CICS resources, releasing 146  
CnnPool database parameter 20  
columns  
    DateTime data type 44  
    default values and bind variables 57  
    delimiting names 86  
    enclosing names in double quotes 54  
    qualification with DirectConnect interface 178  
COM+  
    options 119  
    using TransactionServer object 199  
CommitOnDisconnect database parameter 22  
concurrency control, optimistic 31  
connect strings, ODBC 28  
Connect to Default Profile checkbox in Database Preferences property sheet 208  
Connect to Default Profile database preference 208  
ConnectAs database parameter 23  
connecting to databases, keeping connections open 209  
ConnectOption database parameter 24  
ConnectionString database parameter 28  
CursorLib database parameter 30  
CursorLock database parameter 30  
cursors  
    blocking factor 13  
    blocking factor, Sybase Adaptive Server Enterprise 15  
    blocking factor, Sybase DirectConnect 15  
    keyset-driven, ODBC 31

## Index

- library, ODBC 30
- locking options, ODBC 30
- mixed, ODBC 31
- scrollable, ASE 33
- scrolling options, INFORMIX interfaces 148
- scrolling options, ODBC 31
- setting with ConnectOption database parameter 24
- update characteristics 34
- CursorScroll database parameter 31
- CursorType database parameter 33
- CursorUpdate database parameter 34
- Customer Information Control System (CICS), IBM 146

## D

- Data Definition Language (DDL) statements, SQL 206
- data link file, using in OLE DB 36
- Data Pipeline painter
  - displaying terse error messages 109
  - inserting rows at one time 92
- data source, specifying in OLE DB 37
- Database database parameter 35
- database interfaces
  - database parameters 1
  - database preferences 203
- Database painter, changing SQL terminator character 216
- database parameters
  - and supported database interfaces 1
  - AppName 7
  - Async 8
  - BinTxtBlob 11
  - Block, ODBC 13
  - Block, OLE DB 13
  - Block, Oracle 13
  - Block, Sybase Adaptive Server Enterprise 15
  - Block, Sybase DirectConnect 15
  - CacheAuthentication 16
  - CacheName 16
  - CallEscape 18
  - CharSet 19
  - CnnPool 20
  - CommitOnDisconnect 22
  - ConnectAs 23
  - ConnectOption 24
  - ConnectString 28
  - CursorLib 30
  - CursorLock, ODBC 30
  - CursorScroll, ODBC 31
  - CursorType 33
  - CursorUpdate 34
  - Database 35
  - DataLink 36
  - DataSource 37
  - Date 38
  - DateFormat 41
  - DateTime 42
  - DateTimeAllowed 44
  - DateTimeFormat 46
  - DBConfigSection 47
  - DBGetTime 49
  - DBTextLimit 50
  - DecimalSeparator 51
  - DelimiterIdentifier 54, 86
  - DisableBind 56, 59, 93, 177
  - Driver 60
  - DS\_Alias 61
  - DS\_Copy 63
  - DS\_DitBase 65
  - DS\_Failover 68
  - DS\_Password 70
  - DS\_Principal 72
  - DS\_Provider 73
  - DS\_TimeLimit 75
  - EncryptPassword 77
  - FoDelay 78
  - FoDialog 78
  - FoRetryCount 79
  - FormatArgsAsExp 80
  - GetConnectionOption 82
  - Host 83
  - HostReqOwner 85
  - IdentifierQuoteCharacter 86
  - ImpersonationLevel 88
  - INET\_DBPATH 89
  - INET\_PROTOCOL 90
  - INET\_SERVICE 91
  - Init\_Prompt 92
  - InsertBlock 92
  - IntegratedSecurity 94
  - JavaVM 96
  - KeepAlive 97

- Language 98
- LCID 99
- Locale 100
- Location 102
- Log 102
- LoginTimeout 103
- LowerCaseIdent 103
- MaskPassword 104
- MaxConnect 105
- MixedCase 107
- Mode 108
- MsgTerse 109
- NumbersInternal 112
- NumericFormat 113
- ObjectMode 115
- ODBCU\_CONLIB 116
- OJSyntax 117
- OraMTSConFlgs 119
- PackageProcs 120
- PacketSize 122
- PacketSize, ODBC 121
- PBCatalogOwner 123
- PBMaxBlobSize 126
- PBTrimCharColumns 128
- PBUseProcOwner 129
- PersistEncrypted 131
- PersistSecurityInfo 132
- Properties 133
- ProtectionLevel 134
- Provider 135
- ProviderString 136
- ProxyUserName 137
- PWDialog 127, 138, 140
- PWEncrypt 139
- QualifyPublic 141
- Release 6, 142
- ReleaseConnectionOption 144
- Request 146
- RPCRebind 147, 148
- Scroll 148
- Sec\_Channel\_Bind 149
- Sec\_Confidential 151
- Sec\_Cred\_Timeout 152
- Sec\_Data\_Origin 156
- Sec\_Delegation 157
- Sec\_Keytab\_File 159
- Sec\_Mechanism 161
- Sec\_Mutual\_Auth 163
- Sec\_Network\_Auth 165
- Sec\_Replay\_Detection 167
- Sec\_Seq\_Detection 169
- Sec\_Server\_Principal 170
- Sec\_Sess\_Timeout 172
- ServiceComponents 174
- ShowWarnings 174
- SPCache 175
- SQLCache 176
- SQLQualifiers 178
- StaticBind 179
- StripParmNames 181
- SvrFailover 182
- SystemOwner 183
- SystemProcs 184
- TableCriteria 185
- ThreadSafe 187
- Time 188, 191
- Timeout 21, 192
- TraceFile 194
- TrimSpaces 195, 196
- TRS 197
- URL 197
- UseContextObject 199
- UseProcSyntax 201
- UTF8 201
- database preferences
  - and supported database interfaces 203
  - AutoCommit 205
  - Connect to Default Profile 208
  - Keep Connection Open 209
  - Lock 210
  - Read Only 214
  - Shared Database Profiles 215
  - SQL Terminator Character 216
  - Use Extended Attributes 217
- Database Profile Setup dialog box
  - AutoCommit Mode check box 205
  - Isolation Level box 95, 210
- database profiles
  - connect string for ODBC data sources 28
  - connection pool 20
  - setting Shared Database Profiles database preference 215

## Index

- databases
    - controlling updates 214
    - keeping connections open 209
    - lock values and isolation levels 95, 210
  - DataLink database parameter 36
  - DataSource database parameter 37
  - DataWindow objects
    - asynchronous operations 8
    - getting result set description before retrieval 179
  - Date database parameter 38
  - date format 38, 41
  - DateFormat database parameter 41
  - DateTime data type, as unique key columns 44
  - DateTime database parameter 42
  - DateTime format 42, 46
  - DateTimeAllowed database parameter 44
  - DateTimeFormat database parameter 46
  - DB2 shadow catalogs 183
  - DB2SYSPB.SQL script, and PBCatalogOwner database 125
  - DBA, as Adaptive Server Anywhere stored procedure owner 130
  - DBConfigSection database parameter 47
  - DBGetTime database parameter 49
  - DBMS
    - database parameters supported for each 1
    - database preferences supported for each 203
    - lock values and isolation levels 95, 210
  - DBParm parameters
    - MaxFetchBuffer, Oracle 106
  - DBTextLimit database parameter 50
  - DDL statements, SQL 206
  - decimal separators
    - setting with DecimalSeparator database parameter 51
    - setting with NumericFormat DBParm 114
  - DecimalSeparator database parameter 51
  - DelimitIdentifier database parameter 54, 86
  - describeless retrieval 179
  - dirty reads 213
  - DisableBind database parameter 56, 93, 177
  - DisableUnicode database parameter 59
  - DIT base for Sybase Open Client directory services
    - examples 66
  - Driver database parameter 60
  - DS\_Alias database parameter 61
  - DS\_Copy database parameter 63
  - DS\_DitBase database parameter 65
  - DS\_Failover database parameter 68
  - DS\_Password database parameter 70
  - DS\_Principal database parameter 72
  - DS\_Provider database parameter 73
  - DS\_TimeLimit database parameter 75
  - DSN (data source name) value, in ODBC connect strings 28
- ## E
- EAServer connection cache
    - options 82
    - releasing a connection 137, 144
    - setting 16
  - EAServer, using TransactionServer object 199
  - EncryptPassword database parameter 77
  - error messages, displaying terse 109
  - Euro symbol, with Oracle8i 59
  - extended attribute system tables
    - controlling creation with Use Extended Attributes database preference 217
    - table owner, setting 123
  - extended attribute system tables, controlling updates with Read Only database preference 214
- ## F
- failover, using in Oracle databases 78
  - FoDelay database parameter 78
  - FoRetryCount database parameter 79
  - FormatArgsAsExp database parameter 80
- ## G
- GetConnectionOption database parameter 82
- ## H
- Host database parameter 83
  - HostReqOwner database parameter 85

- I**
- IBM Informix database interface, see Informix database interface 203
  - IdentifierQuoteCharacter database parameter 86
  - identity columns, ADO.NET 47
  - ImpersonationLevel database parameter 88
  - indexes
    - delimiting names 86
    - enclosing names in double quotes 54
  - INET\_DBPATH database parameter 89
  - INET\_PROTOCOL database parameter 90
  - INET\_SERVICE database parameter 91
  - Informix database interface
    - cursor scrolling options, setting 148
    - database parameters 1
    - database preferences 203
    - decimal separator, setting 51
    - INET\_DBPATH database parameter 89
    - INET\_PROTOCOL database parameter 90
    - INET\_SERVICE database parameter 91
    - lock values and isolation levels 211
    - ThreadSafe database parameter 187
  - Init\_Prompt database parameter 92
  - InsertBlock database parameter 92
  - IntegratedSecurity database parameter 94
  - Isolation database parameter 95
  - Isolation Level box in Database Profile Setup dialog box 210
  - Isolation Level in Database Profile Setup dialog box 95
  - isolation levels and lock values 95, 210
    - dynamically controlling in applications 213
- J**
- Java VM, specifying 96
  - JavaVM database parameter 96
  - JDBC database interface
    - database parameters 1
    - database preferences 203
    - database URL, setting 197
    - date format 38
    - DateTime format 42
    - driver name, setting 60
    - EAServer connection cache, options 82
    - EAServer connection cache, releasing a connection 137, 144
    - EAServer connection cache, setting 16
    - error messages, displaying terse 109
    - Java VM, specifying 96
    - lock values and isolation levels 211
    - login timeout, setting 103
    - numeric format, setting 113
    - properties, setting 133
    - Select Tables list, modifying 185
    - time format 188, 191
    - tracing, setting 194
    - TransactionServer object, using 199
- K**
- Keep Connection Open database preference 209
  - KeepAlive database parameter 97
  - keyset-driven cursors, ODBC 31
- L**
- Language database parameter 98
  - LCID database parameter 99
  - Locale database parameter 100
  - Location database parameter 102
  - Lock database preference 210
  - Lock Transaction object property 95, 210
  - lock values and isolation levels 95, 210
    - dynamically controlling in applications 213
  - locking
    - and DBMS isolation levels 95, 210
    - cursors, ODBC 30
    - dirty reads 213
    - dynamically controlling isolation level in applications 213
    - nonrepeatable reads 213
    - phantoms 213
  - Log database parameter 102
  - LOG files, for Adaptive Server 102
  - logical unit of work (LUW) 205
  - LoginTimeOut database parameter 103
  - LowerCaseIdent database parameter 103
  - LUW 205

## M

MaskPassword database parameter 104  
MaxConnect database parameter 105  
MaxFetchBuffer database parameter 106  
mixed cursors, ODBC 31  
MixedCase database parameter 107  
Mode database parameters 108  
MsgTerse database parameter 109

## N

Namespace database parameter 110  
NCharBind database parameter 111  
nonrepeatable reads 213  
NumbersInternal database parameter 112  
NumericFormat database parameter 113

## O

ObjectMode database parameter 115  
ODBC connect strings 28  
ODBC data sources  
    caching SQL statements 176  
    connect string, setting 28  
    cursor library, setting 30  
    cursor locking options, setting 30  
    cursor scrolling options, setting 31  
    data source name (DSN) in ConnectString database parameter 28  
    database parameters 1  
    database preferences 203  
    date format 38  
    DateTime format 42  
    error messages, displaying terse 109  
    inserting rows in Data Pipeline painter 92  
    lock values and isolation levels 211  
    network packet size, setting 121  
    RPCs, rebinding 147, 148  
    time format 188, 191  
ODBC Driver Manager Trace, setting with ConnectOption database parameter 24  
ODBC drivers  
    caching SQL statements 176  
    connect string, setting 28

    cursor library, setting 30  
    cursor locking options, setting 30  
    cursor scrolling options, setting 31  
    database parameters 1  
    database preferences 203  
    error messages, displaying terse 109  
    lock values and isolation levels 211  
    login timeout, setting 103  
    network packet size, setting 121  
    numeric format, setting 113  
    RPCs, rebinding 147, 148  
ODBC interface  
    connect string, setting 28  
    ConnectOption database parameter, using 24  
    cursor blocking factor, setting 13  
    cursor library, setting 30  
    cursor locking options, setting 30  
    cursor scrolling options, setting 31  
    database parameters 1  
    database preferences 203  
    date format 38  
    DateTime format 42  
    decimal separator, setting 51  
    EAServer connection cache, releasing a connection 137, 144  
    EAServer connection cache, setting 16  
    error messages, displaying terse 109  
    inserting rows in Data Pipeline painter 92  
    Jaguar connection cache, options 82  
    lock values and isolation levels 211  
    login timeout, setting 103  
    network packet size, setting 121  
    numeric format, setting 113  
    RPCs, rebinding 147, 148  
    Select Tables list, modifying 185  
    stripping parameter names 181  
    time format 188, 191  
    TransactionServer object, using 199  
ODBCU\_CONLIB database parameter 116  
OJSyntax database parameter 117  
OLE DB database interface  
    access permission 108  
    authentication service, specifying 94  
    caching authentication information 16  
    cursor blocking factor, setting 13  
    data link file, using 35, 36



data protection level, specifying 134  
 data provider, specifying 135  
 data source, specifying 37  
 database parameters 1  
 database preferences 203  
 database server name, identifying 102  
 date format 41  
 DateTime format 46  
 encrypting passwords 77, 78  
 impersonation level 88  
 locale identifier, setting 99  
 lock values and isolation levels 211  
 masking passwords 104  
 maximum blob size, specifying 126  
 prompt, setting 92  
 saving authentication information 132  
 saving encrypted passwords 131  
 SQL Server database, specifying 136  
 timeout, setting 21, 192  
 trimming trailing spaces 128  
 optimistic concurrency control 31  
 Oracle database interface  
   caching SQL statements 176  
   case sensitivity, setting 107  
   COM+ component, options 119  
   cursor blocking factor, setting 13  
   database parameters 1  
   database preferences 203  
   date format 38  
   DateTime format 42  
   decimal separator, setting 51  
   EAServer connection cache, releasing a connection 144  
   EAServer connection cache, setting 16  
   failover 78, 79, 182  
   fetch buffer size, setting 106  
   Jaguar connection cache, options 82  
   listing package objects 120  
   NumbersInternal database parameter 112  
   object mode 115  
   PackageProcs database parameter 120  
   password expired dialog box, displaying 127, 138, 140  
   QualifyPublic database parameter 141  
   Select Tables list, modifying 185  
   ThreadSafe database parameter 187

time format 188, 191  
 TransactionServer object, using 199  
   using Oracle's internal number format 112  
   using the public qualifier 141  
 OraMTSConFlgs database parameter 119

## P

PackageProcs database parameter 120  
 Packet Size database parameter 122  
   used with ODBC 121  
 packet size, network  
   setting 122  
   setting for ODBC data sources 121  
 parenthesis (right), as SQL terminator character 216  
 passwords  
   encrypting in OLE DB databases 77  
   encrypting in Sybase Adaptive Server Enterprise databases 139  
   in ConnectString database parameter 28  
   masking in OLE DB databases 104  
   saving encrypted in OLE DB databases 131  
 PBCatalogOwner database parameter 123  
 PBMaxBlobSize database parameter 126  
 PBNewSPInvocation database parameter 127  
 PBTrimCharColumns database parameter 128  
 PBUseProcOwner database parameter 129  
 PersistEncrypted database parameter 131  
 PersistSecurityInfo database parameter 132  
 phantoms 213  
 Properties database parameter 133  
 ProtectionLevel database parameter 134  
 Provider database parameter 135  
 ProviderString database parameter 136  
 ProxyUserName database parameter 137  
 PWD (password) value, in ODBC connect string 28  
 PWDialog database parameter 138  
 PWEncrypt database parameter 139  
 PWExpDialog database parameter 140

## Q

QualifyPublic database parameter 141

- R**
- Read Only check box in Database Preferences property sheet 214
  - Read Only database preference 214
  - reads, dirty and nonrepeatable 213
  - Release database parameter 142
  - ReleaseConnectionOption database parameter 144
  - Request database parameter 146
  - result sets, getting description before retrieval 179
  - retrieval arguments, as scientific notation 80
  - retrieval, describeless 179
  - RetrieveRow event, coding for asynchronous operations 8
  - ReturnCommandHandle database parameter 148
  - RPCRebind database parameter 147
  - RPCs, rebinding for ODBC data sources 147, 148
- S**
- scientific notation for retrieval arguments 80
  - scope\_identity, using in ADO.NET 47
  - Scroll database parameter 148
  - scrolling options, cursor
    - INFORMIX interfaces 148
    - ODBC 31
  - Sec\_Channel\_Bind database parameter 149
  - Sec\_Confidential database parameter 151
  - Sec\_Cred\_Timeout database parameter 152
  - Sec\_Data\_Origin database parameter 156
  - Sec\_Delegation database parameter 157
  - Sec\_Keytab\_File database parameter 159
  - Sec\_Mechanism database parameter 161
  - Sec\_Mutual\_Auth database parameter 163
  - Sec\_Network\_Auth database parameter 165
  - Sec\_Replay\_Detection database parameter 167
  - Sec\_Seq\_Detection database parameter 169
  - Sec\_Server\_Principal database parameter 170
  - Sec\_Sess\_Timeout database parameter 172
  - security, setting with ConnectOption database parameter 24
  - Select Tables list, modifying 185
  - semicolon, as default SQL terminator character 216
  - ServiceComponents database parameters 174
  - shadow catalogs, creating in DB2 databases 183
  - Shared Database Profiles box in Database Preferences property sheet 215
  - Shared Database Profiles database preference 215
  - shared database profiles, setting up 215
  - ShowWarnings database parameter 174
  - SPCache database parameter 175
  - SQL Data Definition Language (DDL) statements 206
  - SQL files, DB2SYSPB.SQL 125
  - SQL statements
    - allowing DateTime columns as unique key columns 44
    - bind variables 56
    - caching 57, 176
    - issuing inside or outside transactions 205
    - table and column delimiters 86
  - SQL Terminator Character database preference 216
  - SQL terminator character, changing in Database painter 216
  - SQLCache database parameter 176
  - SQLQualifiers database parameter 178
  - SQLSTATE error prefix, suppressing display 109
  - StaticBind database parameter 179
  - stored procedures
    - Adaptive Server Enterprise, displaying 184
    - ODBC, qualifying with owner name 129
    - Oracle, changing SQL terminator character 216
  - StripParmNames database parameter 181
  - SvrFailover database parameter 182
  - Sybase Adaptive Server Anywhere
    - database parameters 1
    - database preferences 203
    - DBA, as stored procedure owner 130
    - stored procedures, qualifying with owner name 130
  - Sybase Adaptive Server Enterprise database interface
    - application name, setting 7
    - character set, setting 19
    - cursor blocking factor, setting 15
    - database parameters 1
    - database preferences 203
    - declaring cursors 33, 34
    - directory services database parameters 61
    - EAServer connection cache, options 82
    - EAServer connection cache, releasing a connection 137, 144
    - EAServer connection cache, setting 16
    - encrypting passwords 139
    - failover 182

- isolation level, dynamically controlling in applications 213
  - language, setting 98
  - locale, setting 100
  - lock values and isolation levels 211
  - logging text and image updates 102
  - password expired dialog box, displaying 127, 138, 140
  - release, setting 6, 142
  - security services database parameters 149
  - Select Tables list, modifying 185
  - TransactionServer object, using 199
  - Sybase DirectConnect interface
    - AutoCommit setting 207
    - character set, setting 19
    - cursor blocking factor, setting 15
    - database parameters 1
    - database preferences 203
    - declaring cursors 34
    - displaying identifier names 103
    - language, setting 98
    - locale, setting 100
    - lock values and isolation levels 211
    - resources, releasing 146
    - Select Tables list, modifying 185
    - setting application name 7
    - specifying host request library name 85
    - table and column name qualification 178
    - trimming trailing spaces 195, 196
  - Sybase Open Client directory services
    - DS\_Alias database parameter 61
    - DS\_Copy database parameter 63
    - DS\_DitBase database parameter 65
    - DS\_Failover database parameter 68
    - DS\_Principal database parameter 70, 72
    - DS\_Provider database parameter 73
    - DS\_TimeLimit database parameter 75
    - Release database parameter 6, 142
    - third-party directory service providers 73
  - Sybase Open Client security services
    - Release database parameter 6, 142
    - Sec\_Channel\_Bind database parameter 149
    - Sec\_Confidential database parameter 151
    - Sec\_Cred\_Timeout database parameter 152
    - Sec\_Data\_Integrity database parameter 154
    - Sec\_Data-Origin database parameter 156
    - Sec\_Delegation database parameter 157
    - Sec\_Keytab\_File database parameter 159
    - Sec\_Mechanism database parameter 161
    - Sec\_Mutual\_Auth database parameter 163
    - Sec\_Network\_Auth database parameter 165
    - Sec\_Replay\_Detection database parameter 167
    - Sec\_Seq\_Detection database parameter 169
    - Sec\_Server\_Principal database parameter 170
    - Sec\_Sess\_Timeout database parameter 172
  - SYSIBM, prohibited as DB2 table owner 125
  - system tables
    - DB2 owner 183
    - DBMS 183
  - SystemOwner database parameter 183
  - SystemProcs database parameter 184
- ## T
- TableCriteria database parameter 185
  - tables
    - controlling updates 214
    - DB2 system owner 183
    - delimiting names 86
    - enclosing names in double quotes 54
    - qualification with DirectConnect interface 178
    - Select Tables list, modifying 185
  - ThreadSafe database parameter 187
  - Time database parameter 188, 191
  - time format 188, 191
  - TimeOut database parameter 21, 192
  - TimeStamp database parameter 192
  - TraceFile database parameter 194
  - transaction log, Adaptive Server 102
  - transaction resources, releasing 146
  - Transaction Router Service 197
  - transactions
    - issuing SQL statements inside or outside 205
    - locking and isolation levels 95, 210
  - TransactionServer object, using 199
  - TrimSpaces database parameter 195
  - TRS database parameter 197
  - TrustedConnection database parameter 196

## **U**

- UID (user ID) value, in ODBC connect string 28
- Unicode
  - Adaptive Server Enterprise 19, 99, 101, 202
  - blob data 11
  - Oracle8i 59
- updating databases, controlling 214
- URL database parameter 197
- URL, using in JDBC 197
- Use Extended Attributes check box in Database Preferences
  - property sheet 217
- Use Extended Attributes database preference 217
- UseContextObject database parameter 199
- UseProcSyntax database parameter 201
- user IDs, in ConnectString database parameter 28
- UTF8 database parameter 201